

**NIST SPECIAL PUBLICATION 1800-27C**

---

# Securing Property Management Systems

---

**Volume C:  
How-To Guide**

**William Newhouse**

Information Technology Laboratory  
National Institute of Standards and Technology

**Michael Ekstrom**

**Jeff Finke**

**Marisa Harriston**

The MITRE Corporation  
McLean, Virginia

September 2020

DRAFT

This publication is available free of charge from

<https://www.nccoe.nist.gov/projects/use-cases/securing-property-management-systems>



1 **DISCLAIMER**

2 Certain commercial entities, equipment, products, or materials may be identified by name or company  
3 logo or other insignia in order to acknowledge their participation in this collaboration or to describe an  
4 experimental procedure or concept adequately. Such identification is not intended to imply special sta-  
5 tus or relationship with NIST or recommendation or endorsement by NIST or NCCoE; neither is it in-  
6 tended to imply that the entities, equipment, products, or materials are necessarily the best available  
7 for the purpose.

National Institute of Standards and Technology Special Publication 1800-27C, Natl. Inst. Stand. Technol.  
Spec. Publ. 1800-27C, 126 pages, September 2020 CODEN: NSPUE2

8 **FEEDBACK**

9 You can improve this guide by contributing feedback. As you review and adopt this solution for your  
10 own organization, we ask you and your colleagues to share your experience and advice with us.

11 Comments on this publication may be submitted to: [hospitality-nccoe@nist.gov](mailto:hospitality-nccoe@nist.gov)

12 Public comment period: September 14, 2020 through October 28, 2020.

13 All comments are subject to release under the Freedom of Information Act.

14 National Cybersecurity Center of Excellence  
15 National Institute of Standards and Technology  
16 100 Bureau Drive  
17 Mailstop 2002  
18 Gaithersburg, MD 20899  
19 Email: [nccoe@nist.gov](mailto:nccoe@nist.gov)

## 20 **NATIONAL CYBERSECURITY CENTER OF EXCELLENCE**

21 The National Cybersecurity Center of Excellence (NCCoE), a part of the National Institute of Standards  
22 and Technology (NIST), is a collaborative hub where industry organizations, government agencies, and  
23 academic institutions work together to address businesses' most pressing cybersecurity issues. This  
24 public-private partnership enables the creation of practical cybersecurity solutions for specific  
25 industries, as well as for broad, cross-sector technology challenges. Through consortia under  
26 Cooperative Research and Development Agreements (CRADAs), including technology partners—from  
27 Fortune 50 market leaders to smaller companies specializing in information technology security—the  
28 NCCoE applies standards and best practices to develop modular, adaptable example cybersecurity  
29 solutions using commercially available technology. The NCCoE documents these example solutions in  
30 the NIST Special Publication 1800 series, which maps capabilities to the NIST Cybersecurity Framework  
31 and details the steps needed for another entity to re-create the example solution. The NCCoE was  
32 established in 2012 by NIST in partnership with the State of Maryland and Montgomery County,  
33 Maryland.

34 To learn more about the NCCoE, visit <https://www.nccoe.nist.gov/>. To learn more about NIST, visit  
35 <https://www.nist.gov>.

## 36 **NIST CYBERSECURITY PRACTICE GUIDES**

37 NIST Cybersecurity Practice Guides (Special Publication 1800 series) target specific cybersecurity  
38 challenges in the public and private sectors. They are practical, user-friendly guides that facilitate the  
39 adoption of standards-based approaches to cybersecurity. They show members of the information  
40 security community how to implement example solutions that help them align more easily with relevant  
41 standards and best practices, and provide users with the materials lists, configuration files, and other  
42 information they need to implement a similar approach.

43 The documents in this series describe example implementations of cybersecurity practices that  
44 businesses and other organizations may voluntarily adopt. These documents do not describe regulations  
45 or mandatory practices, nor do they carry statutory authority.

## 46 **ABSTRACT**

47 Hotels have become targets for malicious actors wishing to exfiltrate sensitive data, deliver malware, or  
48 profit from undetected fraud. Property management systems (PMSes), which are central to hotel  
49 operations, present attractive attack surfaces. This example implementation strives to increase the  
50 cybersecurity of the PMS. The objective was to build a standards-based example implementation that  
51 utilizes readily available commercial off-the-shelf components that enhance the security of a PMS  
52 ecosystem.

53 The NCCoE at NIST built a PMS ecosystem in a laboratory to explore methods for improving the  
54 cybersecurity of a PMS. The scope of the PMS ecosystem included the PMS, a credit card payment  
55 platform, and an analogous ancillary hotel/PMS system. In this example implementation, a physical  
56 access control system was used as the ancillary system.

57 The principal capabilities are to protect sensitive data, to enforce role-based access control, and to  
58 monitor for anomalies. The principal recommendations and best practices are implementing  
59 cybersecurity concepts such as zero trust, moving target defense, tokenization of credit card data, and  
60 role-based authentication.

61 The PMS ecosystem outlined in this guide encourages hoteliers and similar stakeholders to adopt  
62 effective cybersecurity concepts by using standard components that are composed of open-source and  
63 commercially available components.

64 **KEYWORDS**

65 *access control; hospitality cybersecurity; moving target defense; PCI-DSS; PMS; property management*  
66 *system; role-based authentication; tokenization; zero trust architectures*

67 **ACKNOWLEDGMENTS**

68 We are grateful to the following individuals for their generous contributions of expertise and time.

Name	Organization
Sapna George	Cryptonite
Hans Ismirnioglou	Cryptonite
Mike Simon	Cryptonite
Rich Walchuck	Cryptonite
Justin Yackoski	Cryptonite
Katherine Gronberg	Forescout
Timothy Jones	Forescout
Scott Morrison	Forescout

Name	Organization
Shane Stephens	Forescout
Oscar Castiblanco	Häfele
Ryan Douglas	Häfele
Chuck Greenspan	Häfele
Sarah Riedl	Häfele
Harald Ruprecht	Häfele
Roy Wilson	Häfele
Kevin Garrett	Remediant
Paul Lanzi	Remediant
Nicole Guernsey	StrongKey
Pushkar Marathe	StrongKey
Arshad Noor	StrongKey
Bill Johnson	TDi
Pam Johnson	TDi
John Bell	HTNG
Kartikey Desai	MITRE
Eileen Division	MITRE
Karri Meldorf	MITRE

Name	Organization
Paul Ward	MITRE
Trevon Williams	MITRE

69  
70 The Technology Partners/Collaborators who participated in this build submitted their capabilities in  
71 response to a notice in the Federal Register. Respondents with relevant capabilities or product  
72 components were invited to sign a Cooperative Research and Development Agreement (CRADA) with  
73 NIST, allowing them to participate in a consortium to build this example solution. We worked with:

Technology Partner/Collaborator	Build Involvement
Cryptonite	network protection appliance that provides additional layer of protection against cyber attacks
Forescout	visualizes the diverse types of devices connected to the network; enforces policy-based controls
Häfele	physical access control ecosystem that includes door locks, room-key encoding, and management
Remediant	real-time incident monitoring and detection, privilege escalation management, and reporting functions
StrongKey	payment solution appliance that secures credit card transactions and shrinks the payment card industry compliance enclave
TDi	access control platform that secures connections and provides control mechanisms to enterprise systems for authorized users and authorized devices; also monitors activity down to the keystroke

75 **Contents**

76 **1 Introduction ..... 1**

77 1.1 Typographic Conventions ..... 1

78 1.2 Practice Guide Structure ..... 1

79 1.3 PMS Ecosystem Overview ..... 3

80 1.3.1 Usage Scenarios ..... 3

81 1.3.2 Architectural Overview ..... 3

82 1.3.3 General Infrastructure Details and Requirements ..... 4

83 **2 How to Install and Configure ..... 8**

84 2.1 Network Protection Solution—CryptoniteNXT ..... 8

85 2.1.1 Overview of Network Protection Solution ..... 8

86 2.1.2 Network Protection Solution—CryptoniteNXT—Requirements ..... 9

87 2.1.3 Network Protection Solution --CryptoniteNXT—Installation ..... 10

88 2.1.4 Creating Source Groups ..... 11

89 2.1.5 Creating Destination Groups ..... 20

90 2.1.6 Applying Source Groups to End Points ..... 27

91 2.1.7 Applying Destination Group to End Points ..... 31

92 2.1.8 CryptoniteNXT Configuration for the PMS Ecosystem ..... 34

93 2.2 Access Control Platform—TDi ConsoleWorks ..... 37

94 2.2.1 Access Control Platform—TDi ConsoleWorks—Overview ..... 37

95 2.2.2 Access Control Platform—TDi ConsoleWorks—Requirements ..... 38

96 2.2.3 Access Control Platform —TDi ConsoleWorks—Installation ..... 39

97 2.2.4 Add Gateway to GUI ..... 55

98 2.2.5 Add Graphical Connection to End Point ..... 57

99 2.3 Property Management System—Solidres ..... 59

100 2.3.1 Property Management System Overview ..... 59

101 2.3.2 Property Management System—Solidres—Requirements ..... 59

102 2.3.3 Property Management System—Solidres—Installation ..... 60

103 2.3.4 Server Configuration ..... 69

104	2.4	Data Tokenization Appliance–StrongKey .....	72
105	2.4.1	Data Tokenization Appliance–StrongKey–Overview .....	72
106	2.4.2	Data Tokenization Appliance–StrongKey–Requirements .....	73
107	2.4.3	Data Tokenization Appliance–StrongKey—Installation .....	74
108	2.4.4	Payment System Modifications .....	74
109	2.5	Physical Access Control System—Häfele Dialock.....	75
110	2.5.1	Physical Access Control System–Häfele Dialock–Overview.....	75
111	2.5.2	Physical Access Control System–Häfele Dialock–Requirements .....	76
112	2.5.3	Physical Access Control System–Häfele Dialock–Installation .....	77
113	2.5.4	Server Installation .....	78
114	2.5.5	Dialock 2.0 Encoding Station Configuration .....	94
115	2.5.6	Dialock 2.0 Web Setup .....	96
116	2.6	Privileged Access Management System—Remediant SecureONE .....	105
117	2.6.1	Privileged Access Management System–Remediant SecureONE–Overview .....	106
118	2.6.2	Privileged Access Management System–Remediant SecureONE–Requirements .....	107
119	2.6.3	Privileged Access Management System–Remediant SecureONE—Installation .....	108
120	2.6.4	Initial Configuration .....	108
121	2.7	Wireless Network Management—Forescout CounterACT .....	110
122	2.7.1	Wireless Network Management–Forescout CounterACT–Overview .....	111
123	2.7.2	Wireless Network Management–Forescout CounterACT–Requirements.....	112
124	2.7.3	Wireless Network Management–Forescout CounterACT—Installation.....	113
125	2.7.4	DNS Enforcement.....	118
126	2.7.5	Switch Plug-in.....	118
127	2.7.6	Guest Policy.....	121
128	2.8	Virtual Switch—VyOS Configuration .....	133
129	2.9	Integration of Security Components .....	135
130	2.9.1	CryptoniteNXT Integration with CLI End Points.....	135
131	<b>Appendix A List of Acronyms .....</b>		<b>136</b>
132	<b>Appendix B Glossary .....</b>		<b>138</b>

133 **List of Figures**

134 **Figure 1-1a PMS Ecosystem High-Level Architecture .....5**

135 **Figure 1-1b PMS Ecosystem Architecture Detailed .....6**

136 **Figure 2-1 Network Protection Solution in the Reference Architecture .....9**

137 **Figure 2-2 Access Control Platform in the Reference Architecture.....38**

138 **Figure 2-3 Data Tokenization Appliance in the Reference Architecture .....73**

139 **Figure 2-4 Physical Access Control Server in the Reference Architecture .....76**

140 **Figure 2-5 Privileged Access Management System in the Reference Architecture .....107**

141 **Figure 2-6 Wireless Network Management in the Reference Architecture .....112**

142 **List of Tables**

143 **Table 1-1 Architecture List of Components.....4**

144 **Table 1-2 Network Segment Details of the Hospitality Example Lab Build .....6**

145 **Table 1-3 Lab Network Host Record Information.....7**

146 **Table 2-1 Required Destination Groups for CryptoniteNXT Configuration .....35**

147 **Table 2-2 Required Source-Destination Mappings for CryptoniteNXT Configuration.....36**

## 149 1 Introduction

150 The following volume of this guide shows information technology (IT) professionals and security  
151 engineers how we implemented this example solution. We cover all the products employed in this  
152 reference design. We do not re-create the product manufacturers' documentation, which is presumed  
153 to be widely available. Rather, these volumes show how we incorporated the products together in our  
154 environment.

155 *Note: These are not comprehensive tutorials. There are many possible service and security configurations*  
156 *for these products that are out of scope for this reference design.*

### 157 1.1 Typographic Conventions

158 The following table presents typographic conventions used in this volume.

Typeface/Symbol	Meaning	Example
<i>Italics</i>	file names and path names; references to documents that are not hyperlinks; new terms; and placeholders	For language use and style guidance, see the <i>NCCoE Style Guide</i> .
<b>Bold</b>	names of menus, options, command buttons, and fields	Choose <b>File &gt; Edit</b> .
Monospace	command-line input, on-screen computer output, sample code examples, and status codes	<code>mkdir</code>
<b>Monospace Bold</b>	command-line user input contrasted with computer output	<code>service sshd start</code>
<a href="#">blue text</a>	link to other parts of the document, a web URL, or an email address	All publications from NIST's NCCoE are available at <a href="https://www.nccoe.nist.gov">https://www.nccoe.nist.gov</a> .

### 159 1.2 Practice Guide Structure

160 This National Institute of Standards and Technology (NIST) Cybersecurity Practice Guide demonstrates a  
161 standards-based reference design and provides users with the information they need to replicate the  
162 property management system (PMS) ecosystem built in our laboratory. This reference design is modular  
163 and can be deployed in whole or in part.

164 This guide contains three volumes:

- 165       ▪ NIST SP 1800-27A: *Executive Summary*
- 166       ▪ NIST SP 1800-27B: *Approach, Architecture, and Security Characteristics* – what we built and why
- 167       ▪ NIST SP 1800-27C: *How-To Guides* – instructions for building the example solution (**you are**
- 168           **here**)

169 Depending on your role in your organization, you might use this guide in different ways:

170 **Business decision makers, including chief security and technology officers**, will be interested in the

171 *Executive Summary*, NIST SP 1800-27A, which describes the following topics:

- 172       ▪ challenges that enterprises face in making a PMS more secure
- 173       ▪ example solution built at the NCCoE
- 174       ▪ benefits of adopting the example solution

175 **Technology or security program managers** who are concerned with how to identify, understand, assess,

176 and mitigate risk will be interested in NIST SP 1800-27B, which describes what we did and why. The

177 following sections will be of particular interest:

- 178       ▪ Section 3.4, Risk, describes the risk analysis we performed.
- 179       ▪ Section 3.4.3, Security Control Map, maps the security characteristics of this example solution to
- 180           cybersecurity standards and best practices.

181 Section 6.2, Privacy Protections, describes how we used the *NIST Privacy Framework* Subcategories. You

182 might share the *Executive Summary*, NIST SP 1800-27A, with your leadership team members to help

183 them understand the importance of adopting standards-based PMS cybersecurity.

184 **IT professionals** who want to implement an approach like this will find this whole practice guide useful.

185 You can use this How-To portion of the guide, NIST SP 1800-27C, to replicate all or parts of the build

186 created in our lab. This How-To portion of the guide provides specific product installation, configuration,

187 and integration instructions for implementing the example solution. We do not recreate the product

188 manufacturers' documentation, which is generally widely available. Rather, we show how we

189 incorporated the products together in our environment to create an example solution.

190 This guide assumes that IT professionals have experience implementing security products within the

191 enterprise. While we have used a suite of commercial products to address this challenge, this guide does

192 not endorse these particular products. Your organization can adopt this solution or one that adheres to

193 these guidelines in whole, or you can use this guide as a starting point for tailoring and implementing

194 parts of a more secure PMS. Your organization's security experts should identify the products that will

195 best integrate with your existing tools and IT system infrastructure. We hope that you will seek products

196 that are congruent with applicable standards and best practices. Section 1.3.2, Architectural Overview,

197 lists the products that we used and maps them to the cybersecurity controls provided by this reference  
198 solution.

199 Acronyms used in figures and tables are in the appendix List of Acronyms.

## 200 **1.3 PMS Ecosystem Overview**

201 The NCCoE at NIST built an example laboratory environment, known hereafter as the PMS ecosystem, to  
202 explore options available to secure the PMSes used by hotels and other organizations in the hospitality  
203 sector.

### 204 **1.3.1 Usage Scenarios**

205 Securing a PMS requires implementing strong security measures in not only the PMS but also the  
206 components that logically and physically communicate with it. These components include an access  
207 control platform, network protection solutions for enterprise and wireless networks, data tokenization,  
208 and Privileged Access Management (PAM). The example implementation fulfills several use cases to  
209 demonstrate needed functionality of a hotel enterprise, including utilizing secure communication and  
210 tokenization during PMS transactions, creating a room key in a protected manner, and allowing only  
211 approved connections to the PMS.

212 The NCCoE worked with members of the NCCoE Hospitality Community of Interest to develop a set of  
213 use case scenarios to help design and test the PMS ecosystem. For a detailed description of the PMS  
214 ecosystem's architecture and the use cases, see Section 4 in Volume B.

### 215 **1.3.2 Architectural Overview**

216 The *Securing Property Management Systems* high-level reference architecture is illustrated in [Figure 1-](#)  
217 [1a](#) and [Figure 1-1b](#). These figures show the technologies used in the PMS ecosystem. The architecture  
218 displays the authentication mechanisms, protected network zones, privilege management, and  
219 hospitality enterprise functionality.

220 The implementation enforces that only authorized network communications are allowed to and from  
221 the PMS. Three access levels are allowed with the PMS in this build. Unprivileged users, such as guests,  
222 get limited access, e.g., the public-facing web pages for the PMS, and internet access. Privileged  
223 enterprise users, such as front desk employees, get elevated access to the reservation process. For this  
224 build, this is accomplished via a dedicated administrative web page, but this solution will differ based on  
225 the existing PMS configuration of the adopting enterprise. Finally, the access control platform controls  
226 any system-level access to administer the PMS server.

227 In addition to these privilege protections, we used technologies for secure authentication, secure  
228 storage, and secure Wi-Fi.

229 We constructed the example implementation on the NCCoE’s VMware vSphere virtualization operating  
 230 environment. A limited number of tools and technologies used in this build employed physical  
 231 components. We used internet access to connect to remote cloud-based components, while we  
 232 installed software components as virtual servers within the vSphere environment. The physical  
 233 components were connected to the virtual servers through a layer 2 switch. The technology providers  
 234 used in this build offer physical and virtual deployments of their products. Hospitality PMS  
 235 implementations will vary, and the implementation decisions made in this build between virtual and  
 236 physical will not necessarily align with every hospitality organization’s policies and designs.

237 The example build implementation uses the components listed in Table 1-1 and shown in Figure 1-1a  
 238 PMS Ecosystem High-Level Architecture and Figure 1-1b PMS Ecosystem Architecture Detailed.


239 **Table 1-1 Architecture List of Components**

Component	Provider	Installation Guidance
network protection solution	CryptoniteNXT	<a href="#">Section 2.1</a>
access control platform	TDi ConsoleWorks	<a href="#">Section 2.2</a>
property management system	Solidres	<a href="#">Section 2.3</a>
data tokenization appliance	StrongKey	<a href="#">Section 2.4</a>
physical access control system	Häfele Dialock	<a href="#">Section 2.5</a>
privileged access management	Remediant Secure-ONE	<a href="#">Section 2.6</a>
wireless network management	Forescout Counter-ACT	<a href="#">Section 2.7</a>


### 240 1.3.3 General Infrastructure Details and Requirements

241 Figure 1-1a and Figure 1-1b show the lab network architecture that supports the PMS ecosystem. The  
 242 figures show the components, firewalls, and network design of the PMS ecosystem. We separated the  
 243 figures into two figures to make them fit onto the page better with the VLAN (Virtual Local Area  
 244 Network) 2128 device as the connector between the two figures. The installation and configuration  
 245 details for the key components shown in the figures is the focus of this volume of the guide.

246 Figure 1-1a PMS Ecosystem High-Level Architecture



247 **Figure 1-2b PMS Ecosystem Architecture Detailed**



248

249 **1.3.3.1 Network Segmentation and Domain Name System (DNS)**

250 Table 1-2 lists the hospitality example lab build’s network internet protocol (IP) address range for the  
 251 PMS ecosystem. These network addresses were used in the example implementation builds and each  
 252 organization will configure IP addresses to reflect actual network architectures when deployed.

253 **Table 1-2 Network Segment Details of the Hospitality Example Lab Build**

Network	PMS Ecosystem Segments
192.168.0.0/24	hotel guest and employee Wi-Fi
192.168.1.0/24	network demilitarized zone and Wi-Fi security enforcement
192.168.28.0/23	back-end hotel infrastructure secure zone

254

255 In the PMS ecosystem, DNS was configured as shown in Table 1-3, showing host names, fully qualified  
 256 domain names (FQDNs), and IP addresses to facilitate data communication among the components. The  
 257 domain for the PMS ecosystem is hotel.nccoe. Table entries marked with an asterisk are located within  
 258 the CryptoniteNXT secured zone and do not require a static address. [Figure 1-1a](#) and [Figure 1-1b](#) show  
 259 the architecture details with IP addresses.

260 **Table 1-3 Lab Network Host Record Information**

Host Name	FQDN	IP Address
win-hotel	win-hotel.hotel.nccoe	192.168.28.10
Forescout	forescout.hotel.nccoe	192.168.1.43
Tdi	tdi.hotel.nccoe	192.168.29.22*
Remediantso	remediantso.hotel.nccoe	192.168.29.23*
hafelees	hafelees.hotel.nccoe	192.168.29.18*
hafele	hafele.hotel.nccoe	192.168.29.39*
solidres	solidres.hotel.nccoe	192.168.28.194*
admin-solidres	admin-solidres.hotel.nccoe	192.168.29.50*
cryptonitemws	cryptonitemws.hotel.nccoe	192.168.29.49*
front-desk	front-desk.hotel.nccoe	192.168.29.42*
mail	mail.hotel.nccoe	192.168.29.46*

261 The network adapter configuration for the DNS server is as follows:

- 262
- Network Configuration (Interface 1)
    - IPv4 Manual
    - IPv6 Disable
    - IP Address: 192.168.28.10
    - Gateway: 192.168.28.3
    - Netmask: 255.255.255.0
    - DNS Name Servers: 192.168.28.10
- 263
- DNS-Search Domains: hotel.nccoe

## 264 **2 How to Install and Configure**

265 This section of the practice guide contains detailed instructions for installing and configuring all the  
266 products used to build an instance of the example implementation.

### 267 **2.1 Network Protection Solution—CryptoniteNXT**

268 This section of the guide provides installation and configuration guidance for the network protection  
269 solution, which ensures that only valid end points are allowed to connect to the network and the PMS,  
270 and that those end points use the network in an approved manner.

271 CryptoniteNXT is the network protection solution used in the example implementation.

272 When using a network protection solution such as CryptoniteNXT, we recommend installing and setting  
273 it up before installing other resources onto your network. This is because the CryptoniteNXT device  
274 serves as the router and switch for the enterprise network. However, apply the steps to secure the  
275 enterprise, as described in [Section 2.1.8](#), to a component after the component has been separately  
276 installed and configured within the CryptoniteNXT environment.

#### 277 **2.1.1 Overview of Network Protection Solution**


278 CryptoniteNXT is employed here as the network protection solution device and brings zero trust  
279 architecture and moving target defense capabilities to the PMS ecosystem.

280 CryptoniteNXT is a network appliance installed as a physical device in the NCCoE hospitality lab.  
281 Installation instructions are included in the packaging that comes with the CryptoniteNXT device. The  
282 device is also available as a virtual appliance.

283 The CryptoniteNXT device requires that users authenticate using multifactor authentication and allows  
284 only validated connections within the implementation. The device applies a zero trust architecture  
285 philosophy to its protected network zone. Zero trust architecture is an architectural approach that  
286 focuses on data protection and role-based authentication. Its goal is to eliminate unauthorized access to  
287 data, coupled with making the access control enforcement as granular as possible.

288 The moving target defense capability of the CryptoniteNXT device anonymizes IP addresses to prevent a  
289 malicious actor from mapping the enterprise network. The protected network zone controlled by  
290 CryptoniteNXT is shown in the yellow boxes in Figure 2-1.

291 Figure 2-1 Network Protection Solution in the Reference Architecture



292 **2.1.2 Network Protection Solution—CryptoniteNXT—Requirements**

293 The following subsections document the software, hardware, and network requirements for the  
294 network protection solution for version 2.9.1.

295 **2.1.2.1 Hardware Requirements for the Network Protection Solution**

296 CryptoniteNXT was deployed as a physical piece of hardware, provided by the vendor. If a virtual  
297 appliance is utilized, the appliance will require a 20-gigabyte (GB) hard drive, 4 GB of memory, and a

298 virtual central processing unit (CPU). Additionally, Ethernet cables and a serial console cable are  
299 necessary for full setup and configuration.

### 300 *2.1.2.2 Software Requirements for the Network Protection Solution*

301 The CryptoniteNXT device is deployed with its own software requirements fulfilled. However, the first  
302 end points to connect to the device will require Java Runtime Environment to run the CryptoniteNXT  
303 Administration Control Center (ACC) graphical user interface (GUI) and a terminal emulator software,  
304 such as PuTTY, to fully install and configure the device.

### 305 *2.1.2.3 Network Requirements for the Network Protection Solution*

306 CryptoniteNXT requires the necessary physical and virtual hardware to allow all virtual end points to  
307 connect to it, fulfilling the purpose of a network switch and router. A connection is required to the  
308 upstream gateway that leads to the hotel's wireless network, and to the internet. Furthermore,  
309 CryptoniteNXT relies on access to a dedicated local area network (LAN) or VLAN with the sole purpose of  
310 providing intercommunication between the CryptoniteNXT nodes.

## 311 **2.1.3 Network Protection Solution—CryptoniteNXT—Installation**

312 The majority of the installation and setup for the CryptoniteNXT device can be found in the  
313 CryptoniteNXT Unified Installation Guide. IP addresses and host names used in this solution are listed in  
314 [Section 1.3.3](#) of this document. Properly configuring CryptoniteNXT to secure an enterprise requires  
315 creation and application of destination groups (also called access control policies) and source groups. A  
316 destination group defines the connections that are allowed to connect to a given end point. A source  
317 group defines the connections that an end point is allowed to make. Find more information in the  
318 CryptoniteNXT Administration Control Center (ACC) User Manual. [Sections 2.1.4](#) and [2.1.5](#) have detailed  
319 instructions to create and apply a generic source and destination group.

320 The configuration procedure consists of the following steps:


- 321 1. Create a source group to govern what network connections can flow from an end point.
- 322 2. Create a destination group to govern what network connections can flow to an end point.
- 323 3. Apply a source group to a specific end point.
- 324 4. Apply a destination group to a specific end point.
- 325 5. Create and apply the necessary source and destination groups to correctly support the hotel  
326 enterprise, as detailed below.

327 **2.1.4 Creating Source Groups**


328 The following instructions assume that initial installation and configuration of the CryptoniteNXT device  
329 have been completed, as detailed in the CryptoniteNXT Unified Installation Guide. Once completed,  
330 open the CryptoniteNXT ACC GUI executable from a connected end point, and click the Policy tab to  
331 begin the following configuration.

332 In addition to providing guidance on creating a generic source group, the following instructions will  
333 allow authorized external traffic to flow through the CryptoniteNXT device.

- 334 1. In the Cryptonite **Policy** tab, click **Enable Editing**:




- 335
- 336 2. Under the **Source Groups** box, select the green plus button in the top right (hover text: New  
337 Source Group):




338

339


3. Input the desired source group name:



- 340 4. Click **OK**.
- 341 5. Under the **Gateway Nodes** box, select the left-most button (hover text: Assign Gateways to In-
- 342 gress Groups):




- 343
- 344 6. Select the desired gateway under **All Gateways**:



345


346

7. Select the desired source group under **Available Source Groups**:



347

348 8. Click >>:




349

350

9. Click **Save**.

351


10. Click the right-most button (hover text: Assign Gateways to Egress Groups):



352

353

11. Select the desired gateway under **All Gateways**:




354

355

356


12. Under **Available Destination Groups**, select the destination groups from which you wish to draw access policies:



357

358

13. Click >>:




359

360 14. Click **Save**.

## 361 2.1.5 Creating Destination Groups

362 The following instructions detail creation of a generic destination group. They assume the same access  
363 to the CryptoniteNXT ACC GUI as in the previous instructions.


364 1. Click **Enable Editing**:



365

366 2. Under **Access Control Policies**, click the left-most icon depicting a piece of paper and a green  
367 plus sign (hover text: New Destination Group).

368 3. Create the name of a new destination group:



369

370


4. Click **OK**.

371

5. If there is no blank row underneath the destination group, select the newly created destination group, and click the icon that contains only a green plus sign (hover text: New Access Control Policy Entry):

372

373




374

375


376

- Click the small arrow icon in the **Source Groups** cell of the empty row (hover text: Click the arrow button to view/edit the source groups):



377


7. Select all source groups that you want to have this access:



378

379

8. Click **Save**:




380

381

9. Click the **Protocol** cell of the row.

382

10. Select the protocol for which you wish to create an access policy:




383

384

11. Click the **Port Range** cell of the row.

385

12. Input the desired port ranges for the protocol selected in step 10:




386

387

13. If desired, click the IP Range cell to modify this value. This is unused in this implementation.

388

14. Click the **Action** cell of the row:




389

390 15. Set **Action** to **VISIBLE** to allow traffic of the described type; use **INVISIBLE** to block traffic of this  
 391 type.

## 392 2.1.6 Applying Source Groups to End Points

393 The following instructions detail how to add an already-created source group to a specific end point  
 394 within the CryptoniteNXT enclave. They assume the same access to the CryptoniteNXT ACC GUI as in the  
 395 previous instructions.


- 396 1. In the Cryptonite **Policy** tab, click **Enable Editing**.
- 397 2. Locate the box labeled **Endpoints** to the right of the window, and right-click the desired end  
 398 point:



399


400

3. Select Assign Endpoints to Source Groups:



401


4. Find and select the desired end point under **All Endpoints**:



402

403


5. Find and select the desired source group under **Available Source Groups**:



404

405

6. Click >>:




406 7. Click **Save**.

## 407 2.1.7 Applying Destination Group to End Points

408 The following instructions detail how to apply a previously created destination group to a registered end  
409 point.


410 1. In the Cryptonite **Policy** tab, click **Enable Editing**:



411

412 2. Locate the box titled **Endpoints** on the right hand of the screen. Right-click on any of the end  
413 points.


414 3. Select Assign Endpoints to Destination Groups:




415

416

4. Locate and select the desired end point(s) under **All Endpoints**:




417 5. Select the desired destination group(s) under **Available Destination Groups**:



418

419 6. Click >>:



420

421 7. Click **Save**.

## 422 2.1.8 CryptoniteNXT Configuration for the PMS Ecosystem

423 To gain the benefits of a zero trust architecture discussed in Volume B of this document, proper  
 424 configuration of the CryptoniteNXT device is required. Nonuse of the following network restrictions may  
 425 limit network functionality and diminish the security benefits of the architecture. However, improperly  
 426 configured rules can lead to a loss of network functionality. It may be correct for the adopting enterprise  
 427 to install and configure its enterprise architecture and the remaining security architecture before  
 428 applying the final configuration of the CryptoniteNXT device.

429 In this implementation, it is necessary to create the following source groups. If an organization’s desired  
 430 architecture is different from the one described in this document, it is necessary to adapt the following  
 431 instructions to avoid loss of network or security function. First, create the following source groups by  
 432 using instructions from Section 2.1.4.

- 433 ■ Remediant-Web-Access
- 434 ■ Remediant-Access-Domain
- 435 ■ Remediant-Access-Windows
- 436 ■ RDP-Access
- 437 ■ VNC-Access

438       ▪ HafeleES-Access

439       ▪ TDi-Access

440       ▪ Mail-Allowed

441       Create the following destination groups by using the instructions in Section 2.1.5. All rows should be set  
442       to VISIBLE.

443       **Table 2-1 Required Destination Groups for CryptoniteNXT Configuration**

Destination Group	Source Group	Protocol	Port Range
DNS	All Endpoints	TCP (Transport Control Protocol)	53:53
	All Endpoints	UDP (User Datagram Protocol)	53:53
Mail	Mail-Allowed	TCP	25:25
	Mail-Allowed	UDP	25:25
Remediant-Domain	Remediant-Access-Domain	TCP	389:389
	Remediant-Access-Domain	TCP	636:636
	Remediant-Access-Domain	TCP	123:123
Remediant-Linux	Remediant-Access-Linux	TCP	22:22
Remediant-Web	Remediant-Web-Access	TCP	80:80
	Remediant-Web-Access	TCP	443:443
	Remediant-Web-Access	TCP	3000:3000
	Remediant-Web-Access	TCP	22:22
Remediant-Windows	Remediant-Access-Windows	TCP	137:139
	Remediant-Access-Windows	TCP	445:445
Remote-Access-Linux	VNC-Access	TCP	5901:5901
Remote-Access-Windows	RDP-Access	TCP	3389:3389
	RDP-Access	UDP	3389:3389
Solidres-Admin-Web	Verified Endpoints	TCP	80:80
	Verified Endpoints	TCP	443:443
Solidres-Public	All Endpoints, All Users	TCP	80:80

Destination Group	Source Group	Protocol	Port Range
	All Endpoints, All Users	TCP	443:443
TDi-Incoming	TDi-Access	UDP	514:514
	TDi-Access	TCP	5176:5176
	TDi-Access	TCP	443:443
Hafele-HafeleES	HafeleES-Access	TCP	8443:8443

444

445 Apply the source and destination groups to the end points per instructions in Section [2.1.4](#) and Section  
446 [2.1.5](#). In some deployments, the adopting enterprise may have included an all-traffic or similar rule to  
447 facilitate installation of other devices in the protected zone. Remove all-traffic rules that allow elevated  
448 network privileges at this stage.

449 **Table 2-2 Required Source-Destination Mappings for CryptoniteNXT Configuration**

End Point	Source Groups	Destination Groups
Solidres administrator interface	Mail-Allowed	Remediant-Linux Remote-Access-Linux Solidres-Admin-Web Mail
Solidres public web interface		Solidres-Public Remediant-Linux Remote-Access-Linux
enterprise management work- station	Remediant-Web-Access TDi-Access	Remediant-Access-Windows
employee workstations	TDi-Access	
mail server	Mail-Allowed	Mail
Remediant SecureONE	Remediant-Access-Domain Remediant-Access-Linux Remediant-Access-Windows	Remediant-Web
TDi ConsoleWorks	RDP-Access VNC-Access	Remediant-Linux TDi-Incoming

## 450 2.2 Access Control Platform—TDi ConsoleWorks

451 This section of the guide provides installation and configuration guidance for the access control  
452 platform, which gives access control for system administration in the example implementation. The  
453 access control platform performs authentication of user and devices, and provides console access to the  
454 PMS, management workstation, front desk workstations, and Häfele back-end server.

455 TDi ConsoleWorks is the access control platform used in the PMS ecosystem.

### 456 2.2.1 Access Control Platform—TDi ConsoleWorks—Overview


457 The access control platform TDi ConsoleWorks performs the access control functionality in the PMS  
458 ecosystem.

459 TDi ConsoleWorks was deployed as a virtual machine (VM) in the NCCoE hospitality lab. Installation  
460 instructions are available at the TDi Technologies support site, which may be useful if the adopting  
461 enterprise's deployment differs substantially from the one used for this project.

462 TDi ConsoleWorks is employed here to create secure connections to end points. In addition to  
463 streamlining access to network end points such as the PMS and the administrator workstation, it can be  
464 used to audit and track those connections to ensure that privileged access is not abused.

465 The location of the access control platform in the reference architecture is highlighted in Figure 2-2  
466 below.

467 Figure 2-2 Access Control Platform in the Reference Architecture



468

## 469 2.2.2 Access Control Platform—TDi ConsoleWorks—Requirements

470 The following subsections document the software, hardware, and network requirements for the access  
471 control platform for version 5.2-0u1.

### 472 2.2.2.1 Hardware Requirements for Access Control Platform

473 TDi recommends amending hardware requirements for ConsoleWorks depending on the size of the  
474 deployment, but at minimum, allocate 2 GB of storage to the machine.

### 475 *2.2.2.2 Software Requirements for Access Control Platform*

476 TDi ConsoleWorks 5.2 requires an operating system (OS) from the following list.

- 477     ▪ 64-bit RedHat Linux 7.5, 7.5, 8.0, or equivalent
- 478     ▪ Windows Server 2012 R2
- 479     ▪ Windows Server 2016
- 480     ▪ Windows Server 2019

481 This build utilized a Community Enterprise Operating System (CentOS) 7.3 64-bit server.

482 To install TDi ConsoleWorks, access must be available to the machine's command line interface (CLI). It  
483 will also be necessary for network access to be available to the machine's IP address (retrievable via the  
484 ifconfig command) during installation. For this build of TDi ConsoleWorks 5.2, installation is conducted  
485 on a VM in the NCCoE virtual environment.

### 486 *2.2.2.3 Network Requirements of the Access Control Platform*

487 In addition to the described access to the CLI, the access control platform requires network access to the  
488 TDi ConsoleWorks back-end server as well as to any end points to which it will connect. The network  
489 must support secure transmission protocols. TDi ConsoleWorks relies on existing means to connect to  
490 protected end points, such as Secure Shell (SSH) or Remote Desktop Protocol (RDP).

491 Note that use of a zero trust networking solution such as CryptoniteNXT can limit availability of network  
492 resources when improperly configured. For this reason, we recommend setting up and verifying TDi  
493 ConsoleWorks before applying rules on the CryptoniteNXT device, as stated in [Section 2.1.8](#).

## 494 **2.2.3 Access Control Platform —TDi ConsoleWorks—Installation**

495 The installation procedure consists of the following steps:

- 496     1. Download the software.
- 497     2. Run the installation script, customizing options to reflect the enterprise.
- 498     3. Create a secure sockets layer (SSL)-capable invocation of TDi ConsoleWorks and generate an SSL  
499         certificate to match.
- 500     4. Download and apply a license.
- 501     5. Create a gateway to allow GUI functionality.
- 502     6. Create connections to the desired end points within the enterprise.

503 The instructions below rely on the assumed access to the TDi ConsoleWorks CLI. The installation media  
504 file name takes the form `ConsoleWorksSSL-<version>.signed,x86_64.rpm` .

505 If the media is not on the installation target, add it through external media or via the scp command.  
506 Obtaining the installation media requires an account on the TDi Technologies support page and can be  
507 accessed at [https://support.tditechnologies.com/get\\_consoleworks/linux](https://support.tditechnologies.com/get_consoleworks/linux).

508 1. Create a directory in the `/tmp` folder:


509 `mkdir /tmp/conwrks`

510 2. Move the ConsoleWorks installation media to `/tmp/conwrks`:

511 `mv path/to/media /tmp/conwrks`

512 3. Change directory to the `conwrks` directory, and verify that the terminal prompt reflects the  
513 change:

514 `cd /tmp/conwrks`



```
Hospitality@tdi ~]$ cd /tmp/conwrks
Hospitality@tdi conwrks]$
```

515

516 4. Execute the installation media:

517 `yum localinstall consoleworksssl-<version>_x86_64.rpm`



```
Hospitality@tdi conwrks]$ sudo yum localinstall ConsoleWorksSSL-5.1-0U1.signed.x86_64.rpm
Loaded plugins: fastestmirror
Examining ConsoleWorksSSL-5.1-0U1.signed.x86_64.rpm: ConsoleWorksSSL-5.1-0U1.x86_64
Marking ConsoleWorksSSL-5.1-0U1.signed.x86_64.rpm to be installed
Resolving Dependencies
--> Running transaction check
--> Package ConsoleWorksSSL.x86_64 0:5.1-0U1 will be installed
--> Finished Dependency Resolution

Dependencies Resolved

=====
Package                Arch      Version      Repository                               Size
=====
Installing:
ConsoleWorksSSL        x86_64    5.1-0U1      /ConsoleWorksSSL-5.1-0U1.signed.x86_64 350 M
Transaction Summary
-----
Install 1 Package

Total size: 350 M
Installed size: 350 M
Is this ok [y/d/N]:
```

518

519 5. Enter the option `y` to begin the installation.

520 6. Wait for the installation to complete. Upon completion, the text `Installed: Console-`  
521 `worksssl.[VERSION]` should appear:

```

=====
Install 1 Package

Total size: 358 M
Installed size: 358 M
Is this ok [y/d/N]: y
Downloading packages:
Running transaction check
Running transaction test
Transaction test succeeded
Running transaction
Installing : ConsoleWorksSSL-5.1-0U1.x86_64 1/1

The installation of the ConsoleWorks package has completed.
To start using ConsoleWorks, perform the following steps:

 1) Install any license keys you have.

 2) Define an 'invocation' of ConsoleWorks by executing
    /opt/ConsoleWorks/bin/cw_add_invo

 3) Start the ConsoleWorks server by executing
    /opt/ConsoleWorks/bin/cw_start

 4) Use a web browser to connect to the location you defined in cw_add_invo,
    log in with User: console_manager Password: Setup

 5) Register ConsoleWorks. For instructions on registering this ConsoleWorks
    invocation, see the installation guide or the ConsoleWorks online Help.

Verifying : ConsoleWorksSSL-5.1-0U1.x86_64 1/1

Installed:
 ConsoleWorksSSL.x86_64 0:5.1-0U1

Complete!
[hospitality@tdi conwrks]$_

```

522

### 523 2.2.3.1 Create SSL Invocation

- 524 1. Escalate to a super user shell by executing the following command and entering the machine  
525 password:

526 `su`

- 527 2. Verify that the command has executed by seeing that the prompt has changed to `root@tdi`:

```

[hospitality@tdi conwrks]$_ su
Password:
shell-init: error retrieving current directory: getcwd: cannot access parent directories: No such fi
le or directory
shell-init: error retrieving current directory: getcwd: cannot access parent directories: No such fi
le or directory
[root@tdi conwrks]#

```

528

- 529 3. Begin invocation creation with the following command:

530 `/opt/ConsoleWorks/bin/cw_add_invo`

- 531 4. Read the End User License Agreement. Accept by typing `y` followed by the enter key.

- 532 5. Enter the following information, in order. The values used in this implementation are provided  
533 for context but may not be appropriate for your enterprise. Press enter to use the default value  
534 provided by the terminal:

- 535           a. desired console name [HotelConsole]
- 536           b. web service port [5176]
- 537           c. enabled syslog functionality [y]
- 538       6. Verify that the desired values have been entered:

```
This program will add a ConsoleWorks invocation.
Are you sure you want to continue?          [Y]: y
What is the name of this ConsoleWorks       []: HotelConsole

The name should be 1 to 8 characters in length. It should also be
composed of the following characters (A-Z, a-z, 0-9 or _).
Please enter a name that meets the specifications above.

What is the name of this ConsoleWorks       []: Hotel
ConsoleWorks server listens on port        [5176]:

It appears that no other process running on this machine
is already listening on the SYSLOG port (514).

Enable ConsoleWorks listening on SYSLOG port [Y]: y

You have entered the following:
Server Name           : Hotel
Server Port           : 5176
Server Host           : 0.0.0.0
Enable syslog listening: y

Do you want to make any changes [N]: n
```

- 539
- 540       7. If satisfied, type n for no changes.

541

### 542 *2.2.3.2 Create SSL Certificate*

543 These instructions rely on execution of Section 2.2.3.1 and are a continuation of the invocation creation  
544 process. They are separated here for clarity.

- 545       1. Input 1 to allow the SSL invocation creation.

```
Do you accept the terms and conditions of this end user license agreement [N]: y

This program will add a ConsoleWorks invocation.

Are you sure you want to continue? [Y]: y

What is the name of this ConsoleWorks [I]: HotelConsole

The name should be 1 to 8 characters in length. It should also be
composed of the following characters (A-Z, a-z, 0-9 or _).
Please enter a name that meets the specifications above.

What is the name of this ConsoleWorks [I]: Hotel
ConsoleWorks server listens on port [5176]:

It appears that no other process running on this machine
is already listening on the SYSLOG port (514).

Enable ConsoleWorks listening on SYSLOG port [Y]: y

You have entered the following:
Server Name : Hotel
Server Port : 5176
Server Host : 0.0.0.0
Enable syslog listening: y

Do you want to make any changes [N]: n

which: no java in (/usr/local/bin:/bin:/usr/bin:/usr/local/sbin:/usr/sbin:/home/hospitality/.local/b
in:/home/hospitality/bin)
Certificate management for invocation Hotel

[0] Return to /opt/ConsoleWorks/bin/cw_add_invo
[1] Create a new SSL certificate for invocation Hotel

Enter menu choice or 0 to return [0]: 1_
```

546

547 2. Enter the following information, pressing enter after each entry:

548 a. country code

549 b. state or provincial name

550 c. city or locality

551 d. company or organization name

552 e. department name

553 f. FQDN

554 g. email address of the person responsible for the certificate

555 h. password to protect the certificate

556 i. the same password to confirm

557 j. name of the person responsible for the certificate

558 k. the number of days for which the certificate will be valid (730 is the default value)

559

```

Do you want to make any changes [N]: n

which: no java in (/usr/local/bin:/bin:/usr/bin:/usr/local/sbin:/usr/sbin:/home/hospitality/.local/b
in:/home/hospitality/bin)
Certificate management for invocation Hotel

    [0] Return to /opt/ConsoleWorks/bin/cw_add_invo
    [1] Create a new SSL certificate for invocation Hotel

Enter menu choice or 0 to return      [0]: 1

Enter the 2 letter code for your country      [US]: US
Enter the name of your state, province, or regional district      [ ]: Maryland
Enter the name of your city or locality      [ ]: Rockville
Enter the name of your company or organization      [ ]: NCCoE
Enter the name of your department      [ ]: Hospitality
Enter the fully qualified host name for this server      [tdi.hotel.nccoe.hotel.nccoe]: tdi.hotel.nc
coe
Enter the email address of the person responsible for this certificate      [ ]: ██████████
Enter the challenge password for this certificate (min 4 chars., max 20 chars.)      [ ]:
Verify the challenge password for this certificate      [ ]:
Enter the name of the person responsible for this certificate      [ ]: ██████████
Enter the number of days for which this certificate will be valid      [730]: 730
WARNING: can't open config file: /usr/local/ssl/openssl.cnf
Generating a 2048 bit RSA private key
.....++++
.....++++
writing new private key to '/tmp/privkey.pem.tmp'
-----
Certificate management for invocation Hotel

    [0] Return to /opt/ConsoleWorks/bin/cw_add_invo
    [1] Create a new SSL certificate for invocation Hotel
    [2] Remove invocation Hotel SSL certificate

Enter menu choice or 0 to return      [0]: _

```

560

561

3. Input 0 to complete the invocation addition:

```

Do you want to make any changes [N]: n

which: no java in (/usr/local/bin:/bin:/usr/bin:/usr/local/sbin:/usr/sbin:/home/hospitality/.local/b
in:/home/hospitality/bin)
Certificate management for invocation Hotel

    [0] Return to /opt/ConsoleWorks/bin/cw_add_invo
    [1] Create a new SSL certificate for invocation Hotel

Enter menu choice or 0 to return      [0]: 1

Enter the 2 letter code for your country      [US]: US
Enter the name of your state, province, or regional district      [ ]: Maryland
Enter the name of your city or locality      [ ]: Rockville
Enter the name of your company or organization      [ ]: NCCoE
Enter the name of your department      [ ]: Hospitality
Enter the fully qualified host name for this server      [tdi.hotel.nccoe.hotel.nccoe]: tdi.hotel.nc
coe
Enter the email address of the person responsible for this certificate      [ ]: ██████████
Enter the challenge password for this certificate (min 4 chars., max 20 chars.)      [ ]:
Verify the challenge password for this certificate      [ ]:
Enter the name of the person responsible for this certificate      [ ]: ██████████
Enter the number of days for which this certificate will be valid      [730]: 730
WARNING: can't open config file: /usr/local/ssl/openssl.cnf
Generating a 2048 bit RSA private key
.....++++
.....++++
writing new private key to '/tmp/privkey.pem.tmp'
-----
Certificate management for invocation Hotel

    [0] Return to /opt/ConsoleWorks/bin/cw_add_invo
    [1] Create a new SSL certificate for invocation Hotel
    [2] Remove invocation Hotel SSL certificate

Enter menu choice or 0 to return      [0]: 0

```

562 *2.2.3.3 Apply License*

563 The following instructions rely on continued access to the command line interface (CLI) of the TDi  
564 ConsoleWorks device.

- 565 1. Execute the shell script provided as the license by TDi Technologies:



```
[root@tdi consoleworks]# sh NIST_190408000.sh _
```

566

- 567 2. Input `y`:

```
[root@tdi conwrks]# sh NIST_19040000.sh
This will install the ConsoleWorks license file(s)
in /etc/TDI_licenses/*.lic

Are you sure you want to continue [Y]: Y

ConsoleWorks licenses successfully installed
[root@tdi conwrks]# _
```

568

#### 569 *2.2.3.4 Start-Up*

- 570 1. Execute the following command, and note the address and port provided in the console re-
- 571 sponse:

572 `/opt/ConsoleWorks/bin/cw_start Hotel`

```
root@tdi conwrks]# /opt/ConsoleWorks/bin/cw_start Hotel
which: no java in (/usr/local/bin:/bin:/usr/bin:/usr/local/sbin:/usr/sbin:/home/hospitality/.local/bin:/home/hospitality/bin)
Attempting to start invocation Hotel...
ConsoleWorks invocation Hotel started.
  Logfile: /opt/ConsoleWorks/Hotel/log/Hotel.out
  URL: http://tdi.hotel.nccoe:5176
root@tdi conwrks]# _
```

573


574 2. Execute the following command:

575


```
/opt/ConsoleWorks/bin/cw -setsid Hotel
```

```
root@tdi conwrks]# /opt/ConsoleWorks/bin/cw -setsid Hotel
2019/04/16 10:44:28 EDT: ConsoleWorks Major Version 5, Minor Version 1, Patch Version 0, Update Version 1
2019/04/16 10:44:28 EDT: %Server image identification is U5.1-0u1-180614LxE
2019/04/16 10:44:28 EDT: %Server expected library identification is 5,1,0:5.1-0u1:18.06.14
2019/04/16 10:44:28 EDT: %Server startup time is 2019/04/16 10:44:28
2019/04/16 10:44:28 EDT: %Server logging configuration file: (internal fallback)
2019/04/16 10:44:28 EDT: %Environment variable CONWRKS_NAME not found - setting to DEFAULT
2019/04/16 10:44:28 EDT: ? *** The ConsoleWorks environment is not properly set up. Specifically, the
2019/04/16 10:44:28 EDT: definition of CONWRKS_ROOT is not present. ConsoleWorks is unable to
operate
2019/04/16 10:44:28 EDT: until this environment is established. Please use the defined startup
facility
2019/04/16 10:44:28 EDT: to start ConsoleWorks. If you are unable to resolve this issue
2019/04/16 10:44:28 EDT: after confirming that your system is properly configured, then please
2019/04/16 10:44:28 EDT: contact TDI Support per the terms of your support agreement
root@tdi conwrks]# _
```

- 576 3. On another machine, open the web page provided in step 1 or the IP followed directly by the  
577 port number:




- 578  
579 4. Log in with default credentials console\_manager/Setup:




580

581

5. Change the default password, and click **Login**:




582 6. Click Register Now:



583

584 7. Fill out contact details, and click **Register Online**:



585

### 586 2.2.3.5 GUI Gateway Installation

587 1. Ensure that the following packages are installed via `$yum install [pkg_name]`, where [pkg\_name]  
588 is:

589 -freerdp-lib3

590 -uid

591 -cairo

592 -libvncserver

593 -libpng12

594 -freerdp-plugins

595 -net-tools

596 -openssh-clients

597 -open-vm-tools

```
root@tdi comwks18# yum install freerdp-libs_
```

598

599 2. Type `y` to allow installation:

```
Loaded plugins: fastestmirror
Repodata is over 2 weeks old. Install yum-cron? Or run: yum makecache fast
base                                     | 3.6 kB  00:00:00
extras                                  | 3.4 kB  00:00:00
updates                                 | 3.4 kB  00:00:00
(1/2): extras/7/x86_64/primary_db       | 200 kB  00:00:00
(2/2): updates/7/x86_64/primary_db     | 5.0 MB  00:00:00
Loading mirror speeds from cached hostfile
 * base: mirrors.oi.tu.ac.uk
 * extras: mirror.metrocast.net
 * updates: ftp.usg.iu.edu
Resolving Dependencies
--> Running transaction check
--> Package freerdp-libs.x86_64 0:1.0.2-15.e17_6.1 will be installed
--> Processing Dependency: libxkbfile.so.10(64bit) for package: freerdp-libs-1.0.2-15.e17_6.1.x86_64
--> Running transaction check
--> Package libxkbfile.x86_64 0:1.0.9-3.e17 will be installed
--> Finished Dependency Resolution

Dependencies Resolved

=====
Package                Arch          Version           Repository        Size
=====
Installing:
freerdp-libs           x86_64        1.0.2-15.e17_6.1 updates           224 k
Installing for dependencies:
libxkbfile             x86_64        1.0.9-3.e17      base              83 k
=====

Transaction Summary
=====
Install 1 Package (+1 Dependent package)

Total download size: 307 k
Installed size: 874 k
Is this ok [y/d/N]: y
```

600

601 3. Repeat steps 1 and 2 for all other packages in the list:

```

Package                Arch           Version          Repository        Size
-----
Installing:
freerdp-libs           x86_64         1.0.2-15.e17_6.1 updates          224 k
Installing for dependencies:
libxkbfile             x86_64         1.0.9-3.e17     base              83 k

Transaction Summary
-----
Install 1 Package (+1 Dependent package)

Total download size: 307 k
Installed size: 874 k
Is this ok [y/d/N]: y
Downloading packages:
Delta RPMs disabled because /usr/bin/applydelta not installed.
(1/2): libxkbfile-1.0.9-3.e17.x86_64.rpm | 83 kB 00:00:00
(2/2): freerdp-libs-1.0.2-15.e17_6.1.x86_64.rpm | 224 kB 00:00:00
-----
Total | 696 kB/s | 307 kB 00:00:00
Running transaction check
Running transaction test
Transaction test succeeded
Running transaction
  Installing : libxkbfile-1.0.9-3.e17.x86_64 | 1/2
  Installing : freerdp-libs-1.0.2-15.e17_6.1.x86_64 | 2/2
  Verifying  : libxkbfile-1.0.9-3.e17.x86_64 | 1/2
  Verifying  : freerdp-libs-1.0.2-15.e17_6.1.x86_64 | 2/2

Installed:
  freerdp-libs.x86_64 0:1.0.2-15.e17_6.1

Dependency Installed:
  libxkbfile.x86_64 0:1.0.9-3.e17

Complete!
[root@tdi ~]# _

```

602

603

604

4. Download *gui\_gateway-0.9.7-3.x86\_64.rpm* (or the latest version), and place on the TDi back-end server:

```

[root@tdi ~]# ls /tmp/comarks
gui_gateway-0.9.7-3.x86_64.rpm
[root@tdi ~]# _

```

605

606

607

5. Install with this command:

```
rpm -ivh gui_gateway-0.9.7-3.x86_64.rpm
```

```
[root@tdi consoleworks]# rpm -ivh gui_gateway-0.9.7-3.x86_64.rpm _
```

608

- 609 6. Execute the following command if you are conducting a local installation, where the gateway is  
610 on the same server as the TDi ConsoleWorks invocation:

611

```
/opt/gui_gateway/install_local.sh
```

```
[root@tdi gui_gateway]# bash /opt/gui_gateway/install_local.sh
Starting gui_gatewayd: gui_gatewayd[2548]: INFO: GUI Gateway daemon (gui_gatewayd) version 0.
9.7 started
SUCCESS
[root@tdi gui_gateway]# _
```

612

- 613 7. Execute the following to start the gateway:

614

```
service gui_gatewayd start
```


```
[root@tdi gui_gateway]# service gui_gatewayd start
Starting gui_gatewayd: SUCCESS
[root@tdi gui_gateway]#
```

615

## 616 2.2.4 Add Gateway to GUI

617 The instructions below are executed on a separate virtual or physical machine that has network access  
618 to the TDi ConsoleWorks back-end server through the previously configured web port. The web service  
619 is accessed through a web browser. The user must navigate to [TDi Domain Name].[Hotel  
620 Domain]:[Port Number] if DNS has been configured for the enterprise or to [TDi IP Address]:[Port  
621 Number] if DNS has not been configured.

- 622 1. Authenticate to the web portal with the `console_manager` account.
- 623 2. Once authenticated, expand the side menu by clicking **Graphical** and then **Gateways**. Click **Add:**



624

625 3. Enter the desired values for the graphical gateway. The values used for this architecture are provided but may not be the correct values for your enterprise.


626

627 a. Name [GGateway]

628 b. Description [Locally hosted Graphical Gateway]

629 c. Host [localhost]

630 d. Port [5172]



631


632 4. Click **Save**.

## 633 2.2.5 Add Graphical Connection to End Point

634 1. In the sidebar, choose **Graphical > Add**.


635 2. For a given system in your organization to which TDi ConsoleWorks will connect, input the  
 636 information below. The connection information to the management workstation in the example  
 637 architecture is provided for reference.

- 638 a. Device Name [MANAGEMENT\_WORKSTATION]
- 639 b. Description [Management Console for Various Security Components]
- 640 c. Device Identifier [CRYPTONITEMWS]
- 641 d. Connection Type [RDP]
- 642 e. DNS Host Information [cryptonite-mws.hotel.nccoe]
- 643 f. Port number [3389]
- 644 g. Username [Administrator]
- 645 h. Password
- 646 i. Domain [hotel.nccoe]



647

- 648 3. Repeat step 3 for all end points in the organization that should be connected to the access control  
 649 platform, including the PMS:



## 650 2.3 Property Management System—Solidres

651 This section of the guide provides installation and configuration guidance for the property management  
652 system, which supplies the core administrative and enterprise function of the hotel. In addition to  
653 booking and payment, property management systems provide a variety of functions and services for  
654 guests and hotel employees. The property management system employed by a hotel, as well as its  
655 specific configurations, depends on the needs of the adopting enterprise. The PMS installation below is  
656 included to demonstrate the completeness of the architecture but will not necessarily reflect the correct  
657 choices for the adopting enterprise.

658 Solidres is the PMS used in the PMS ecosystem. It is the only component that we purchased for this  
659 project.

### 660 2.3.1 Property Management System Overview

661 The Solidres PMS provides the back-end enterprise functionality of a hotel in the PMS ecosystem.

662 The Solidres PMS was built to sit next to a credit card payment platform. A physical access control  
663 system was used as the ancillary system. The security technologies implemented add security controls  
664 to protect sensitive data, enforce role-based access control, and monitor for anomalies.

### 665 2.3.2 Property Management System—Solidres—Requirements

666 The following subsections document the software, hardware, and network requirements for the PMS.

#### 667 *2.3.2.1 Hardware Requirements for the Property Management System*

668 We deployed Solidres on a virtual machine with 4 CPUs, 8 GB of memory, and a 100 GB hard drive. The  
669 proper specifications will depend on a hotel's enterprise requirements of its PMS.

#### 670 *2.3.2.2 Software Requirements for the Property Management System*

671 This build utilized an Ubuntu 18.04 OS. The build employed Solidres for Joomla, utilizing Joomla 3.9.0.

672 To install Solidres, access must be available to the machine's CLI. Network access must also be available  
673 to the machine's IP address (retrievable via the ifconfig command) for installation and later operation of  
674 the PMS. We recommend internet access during installation to allow the required dependencies to  
675 install. For this build of Solidres, we installed on a VM in the NCCoE virtual environment.

#### 676 *2.3.2.3 Network Requirements for the Property Management System*

677 In addition to access to the CLI, the PMS requires network access to be available from any machine that  
678 will connect to it. This will likely include any front desk and administrator workstations that will conduct  
679 booking, reservation management, and related functions.

680 Please note that a zero trust networking solution such as CryptoniteNXT can limit availability of network  
681 resources when improperly configured. For this reason, we recommend setting up and verifying Solidres  
682 before applying the associated rules on the CryptoniteNXT device, as seen in [Section 2.1.8](#).

### 683 2.3.3 Property Management System–Solidres–Installation

684 The installation procedure consists of the following steps:

- 685 1. Install NGINX.
- 686 2. Install MariaDB.
- 687 3. Install Joomla.
- 688 4. Configure the Joomla installation.
- 689 5. Download and install Solidres.
- 690 6. Configure the server to allow remote access and secure authentication.

691 The instructions below rely on assumed access to the Solidres CLI. The server must have either internet  
692 access or the required installation media supplied to it by another machine.

- 693 1. Update current software packages:

694 `sudo apt-get update && sudo apt-get upgrade -y`

- 695 2. Run the following command to install the NGINX web server and Hypertext Preprocessor (PHP)  
696 dependencies:

697 `sudo apt-get install nginx php7.1-cli php7.1-gd php7.1-opcache php7.1-mysql`  
698 `php7.1-json php7.1-mcrypt php7.1-xml php7.1-curl -y`

- 699 3. To ensure that the server is running, use the following command (with expected output also  
700 shown):

701 `sudo systemctl status nginx`


- 702 4. To visually confirm accessibility and that the server is running properly, use a browser to  
703 navigate to `http://localhost`. The following page should appear:



715 `sudo apt install mariadb-server -y`

716 7. Check that the MariaDB service is running (expected output shown):

717 `sudo systemctl status mariadb`

A terminal window showing the output of the command 'sudo systemctl status mariadb'. The output indicates that the mariadb.service is active (running) and provides details about its status, including the loaded path, active state, and various process logs. The status is 'active (running) since Tue 2019-04-23 05:55:34 EDT; 39min ago'. The main PID is 790 (mysqld) and the status is 'Taking your SQL requests now...'.

```
hospitality@hospitality:~$ sudo systemctl status mariadb
● mariadb.service - MariaDB 10.1.38 database server
   Loaded: loaded (/lib/systemd/system/mariadb.service; enabled; vendor preset: enabled)
   Active: active (running) since Tue 2019-04-23 05:55:34 EDT; 39min ago
     Docs: man:mysqld(8)
           https://mariadb.com/kb/en/library/systemd/
   Process: 967 ExecStartPost=/bin/sh -c systemctl unset-environment _WSREP_START_POSITION (code=e
   Process: 963 ExecStartPost=/etc/mysql/debian-start (code=exited, status=0/SUCCESS)
   Process: 690 ExecStartPre=/bin/sh -c [ ! -e /usr/bin/galera_recovery ] && VAR= || VAR=`usr/b
   Process: 667 ExecStartPre=/bin/sh -c systemctl unset-environment _WSREP_START_POSITION (code=ex
   Process: 653 ExecStartPre=/usr/bin/install -m 755 -o mysql -g root -d /var/run/mysqld (code=exi
   Main PID: 790 (mysqld)
     Status: "Taking your SQL requests now..."
     Tasks: 27 (limit: 4915)
    CGroup: /system.slice/mariadb.service
           └─790 /usr/sbin/mysqld
```

718  
719 8. We recommend running the following command to help improve the security of a MariaDB  
720 installation:

721 `sudo mysql_secure_installation`

722 9. Running the secure installation script will generate the following prompts. These are the  
723 recommended responses:

724 10. Enter current password for root [press enter for none]. Enter password and press enter.

725 11. Set root password? [Y/n]. Press Y

726 12. Enter a secure password twice.

727 13. Remove anonymous users? [Y/n]. Press Y

728 14. Disallow root login remotely? [Y/n]. Press Y

729 15. Remove test database and access to it? [Y/n]. Press Y

730 16. Reload privilege tables now? [Y/n]. Press Y

### 731 *2.3.3.1 Confirm the version of MariaDB*

732 1. Log in to the database by using the following command (you will be prompted for a password; it  
733 is the password that was set in step 9e above):

734 `sudo mysql -u root -p`

735 Please note that this is the command that will be used to access the database anytime from the  
736 command line, as shown here:

```
hospitality@hospitality:~$ sudo mysql -u root -p
Enter password:
Welcome to the MariaDB monitor.  Commands end with ; or \g.
Your MariaDB connection id is 35
Server version: 10.1.38-MariaDB-0ubuntu0.18.04.1 Ubuntu 18.04

Copyright (c) 2000, 2018, Oracle, MariaDB Corporation Ab and others.

Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.

MariaDB [(none)]>
```

737  
738 2. To check the version of the running mariadb service, enter the following command:

```
739         select version();
```

### 740 *2.3.3.2 Create the Joomla database*

741 1. Log in to the MariaDB server by using this command, and create a database called **joomladb**  
742 (when prompted, enter the previously set root password):

```
743         sudo mysql -u root -p
744         create database joomladb
```

745 2. Create a database user called **joomlauser** with a new password (that is ideally different from any  
746 other password(s) you may be using):

```
747         create user `joomlauser`@'localhost' identified by `[STRONG PASSWORD]`;
```

748 3. Then grant full access to the database to this new user:

```
749         grant all on joomladb.* to `joomlauser`@'localhost' identified by
750         `[STRONG PASSWORD]`;
```

751 4. Last, save the changes and exit the server:

```
752         flush privileges;
753         exit;
```

### 754 *2.3.3.3 Download the Latest Release of Joomla*

755 1. Use this command to download the latest release of Joomla [The current version may not be  
756 reflected in the document, but you can update the version by using the version used here]:

```
757         cd tmp && wget https://github.com/joomla/joomla-cms/releases/download/3.9.10/Joomla_3.9.10-
758         Stable-Update_Package.zip
```

759 2. Install the unzip tool to unzip the downloaded Joomla zip file if needed:

```
760         sudo apt-get install unzip
```

761 3. Make a new directory for Joomla:

```
762     mkdir -p /var/www/html/joomla
```

763 4. Unzip Joomla into the new directory:

```
764     sudo unzip Joomla*.zip -d /var/www/html/joomla
```

765 5. Now run these commands to give the proper permissions to Joomla's directory:

```
766     sudo chown -R www-data:www-data /var/www/html/joomla
```

```
767     sudo chmod -R 755 /var/www/html/joomla
```

768

### 769 *2.3.3.4 Get the Joomla Website Ready*

770 1. Create a new configuration file titled *joomla*:

```
771     nano /etc/nginx/sites-available/joomla
```

772 2. Add the following text into the file:

```
773     server {
774         listen 80;
775         server_name _;
776         rewrite ^/(.*)$ https://$server_name$request_uri;
777     }
778
779         server {
780             listen 443 ssl;
781             server_name _;
782             ssl_certificate /etc/ssl/certs/nginx-selfsigned.crt;
783             ssl_certificate /etc/ssl/certs/nginx-selfsigned.crt;
784
785             root /var/www/html/joomla;
786             index index.php;
787             location ^~ /administrator {
788                 # Change to reflect your administrative LANS
789                 allow from 192.168.28.0/24;
790                 allow from 192.168.29.0/24;
```

```
790             deny all;
791         }
792
793         location / {
794             try_files $uri $uri/ /index.php?$args;
795         }
796
797         location ~ /\.php$ {
798             include snippets/fastcgi-php.conf;
799             fastcgi_pass unix:/var/run/php/php7.1-fpm.sock;
800             fastcgi_param SCRIPT_FILENAME          $docu-
801             ment_root$fastcgi_script_name;
802             include fastcgi_params;
803         }
804     }
```

804 3. Check the NGINX configuration file:

```
805     nginx -t
```

806 4. Enable your NGINX configuration:

```
807     sudo ln -s /etc/nginx/site-available/joomla /etc/nginx/site-enabled/
```

808 5. Restart the NGINX and PHP service:


```
809     sudo systemctl restart nginx php7.1-fpm
```

810 6. To allow persistence, enable the services if they are not already:

```
811     sudo systemctl enable nginx php7.1-fpm
```

### 812 *2.3.3.5 Finish Installation*

813 1. In a web browser, navigate to <http://localhost>. The following screen should appear. Type in the  
814 information requested, then click **Next**:



Joomla! is free software released under the GNU General Public License.

1 Configuration 2 Database 3 Overview

Select Language: English (United States) [Next](#)

### Main Configuration

Site Name \*   
Enter the name of your Joomla! site.

Description   
Enter a description of the overall website that is to be used by search engines. Generally, a maximum of 20 words is optimal.

Site Offline:  Yes  No  
Set the site Frontend offline when installation is completed. The site can be set online later on through the Global Configuration.

#### Super User Account Details

Email \*   
Enter an email address. This will be the email address of the website Super User.

Username \*   
Set the username for your Super User account.

Password \*   
Set the password for your Super User account and confirm it in the field below.

Confirm Administrator Password \*


[Next](#)

815

816

817

2. Type in the requested information so that Joomla can connect to the Joomla database in the MariaDB server. Then click **Next**:



Joomla! is free software released under the GNU General Public License.

1 Configuration 2 Database 3 Overview

### Database Configuration

[Previous](#) [Next](#)

Database Type \*   
This is probably "MySQL".

Host Name \*   
This is usually "localhost" or a name provided by your host.

Username \*   
Either a username you created or a username provided by your host.

Password   
For site security using a password for the database account is mandatory.

Database Name \*    
Some hosts allow only a certain DB name per site. Use table prefix in this case for distinct Joomla! sites.


Table Prefix \*   
Create a table prefix or use the randomly generated one. Ideally four or five characters long, it may only contain alphanumeric characters and MUST end in an underscore. Make sure that the prefix chosen is not already used by other tables.

Old Database Process \*    
"Backup" or "Remove" any existing tables from former Joomla! installations with the same "Table Prefix".

[Next](#)

818

819 3. Select the appropriate options, then click **Install**.



820

821 4. At <http://localhost>, there should be a welcome landing page similar to the image below.



822

823 5. To access Joomla's admin portal, go to <http://localhost/administrator>, and something like the  
824 image below should appear:



825

826

827

6. First, start by making sure that the system has versions of the required Solidres components that are at least as recent as the versions listed on the following Solidres website:

828

829

<https://www.solidres.com/documentation/joomla-documentation/12-installation/10-technicalrequirements>

830

7. Download the most recent stable version of Solidres from this site:

831

<https://www.solidres.com/download/show-all-downloads/solidres>

832

8. Click the blue **View files** button:




833

834

835

836

9. Scroll down until you see content resembling the following. Identify the *Solidres\_Full\_Package\_v2.x.x.zip* and click the blue **Download now** button. Because this is a zip file, you will need to unzip it; you can store it anywhere on your system:



837

838 10. Follow the installation instructions at this website:

839 <https://www.solidres.com/documentation/joomla-documentation/12->  
840 [installation/11installation](https://www.solidres.com/documentation/joomla-documentation/12-installation/11installation). You will need to first use a web browser, navigate to  
841 <http://localhost/administrator>, sign in using previously created Joomla administrator  
842 credentials, then follow the instructions at the website.

843 11. Once installation is complete, follow the initial configuration instructions for Solidres:

844 [https://www.solidres.com/documentation/joomla-documentation/12-](https://www.solidres.com/documentation/joomla-documentation/12-installation/12-)  
845 [initialconfiguration](https://www.solidres.com/documentation/joomla-documentation/12-installation/12-initialconfiguration)

## 846 2.3.4 Server Configuration

### 847 2.3.4.1 Firewall Configuration

848 1. Install ufw and run the following commands:

```
849     ufw enable  
850     ufw allow http  
851     ufw allow https  
852     ufw allow ssh  
853     ufw allow 1433/tcp  
854     ufw default deny incoming
```

### 855 2.3.4.2 Active Directory Configuration

856 Please refer to the resource below for assistance with the active directory configuration.

857 <https://www.smbadmin.com/2018/06/connecting-ubuntu-server-1804-to-active.html>

858 1. Install the utilities by using this command:

```
859 sudo apt install -y realmd krb5-user samba-common-bin adcli sssd sssd-  
860 tools libnss-sss libpam-sss
```

861 2. For the installation prompts, enter your domain name, then the fully qualified name of your Ac-  
862 tive Directory server twice.

863 3. Edit the file `/etc/krb5.conf` and add:

```
864 [libdefaults]  
865 dns_lookup_kdc = true  
866 dns_lookup_realm = true
```

867 **NOTE:** This may apply if the `samba-common-bin` back end depends on `samba` on your  
868 system:

```
869 sudo systemctl stop samba-ad-dc  
870 sudo systemctl unmask samba-ad-dc  
871 sudo systemctl disable samba-ad-dc
```

872 4. Generate a Kerberos key by using this command:

```
873 kinit Administrator (or any domain admin in your Active Directory)
```

874 5. Check if the command worked by using `klist`. If the command returns anything, it should have  
875 worked:

```
hospitality@mail:~$ kinit Administrator  
Password for Administrator@HOTEL.NCCOE:  
hospitality@mail:~$ klist  
Ticket cache: FILE:/tmp/krb5cc_1000  
Default principal: Administrator@HOTEL.NCCOE  
  
Valid starting Expires Service principal  
07/11/2019 07:57:18 07/11/2019 17:57:18 krbtgt/HOTEL.NCCOE@HOTEL.NCCOE  
renew until 07/12/2019 07:57:13  
hospitality@mail:~$
```

876


877 6. Create the file `/etc/realm.conf` and add:

```
878 [users]  
879 default-home = /home/%D/%U  
880 default-shell = /bin/bash  
881 [active-directory]  
882 default-client = sssd
```

```
883         os-name = Ubuntu
884         os-version = 18.04
885
886     [service]
887         automatic-install = no
888
889     [mydomain.com]
890         fully-qualified-names = yes
891         automatic-id-mapping = no
892         user-principal = yes
893         manage-system = yes
```

7. Run the following command:

```
894     sudo pam-auth-update
```



- 895
8. Run the following command:

```
897     realm discover -v [DOMAIN NAME]
898     sudo realm join -U Administrator
```

9. Edit the `/etc/sss/sss.conf` and modify:

```
900     services = nss, pam, ssh
901
902     [domain/DOMAIN NAME]
```

```
903         ldap_id_mapping = True
904         use_fully_qualified_names = False
905         ldap_user_ssh_public_key = altSecurityIdentities
```

906 10. Edit the file `/etc/pam.d/common-account` and add the following line:

```
907         session    required    pam_mkhomedir.so    skel=/etc/skel/    umask=0022
```

908 11. Restart the `sssd` service:

```
909         sudo systemctl restart sssd
```

910 12. After resetting the service, check if you can utilize the Active Directory server to log in to the do-

911 main:

```
912         su - [ACTIVE DIRECTORY USER]
```

## 913 2.4 Data Tokenization Appliance—StrongKey

914 This section of the guide provides installation and configuration guidance for the data tokenization  
915 appliance, which supplies tokenization and secure storage capabilities in the example implementation. It  
916 protects payment card data in transactions in and around the property management system and can be  
917 further used to support multifactor authentication.

918 A cryptographic domain on StrongKey Tellaro 3.x is the data tokenization appliance in the example  
919 implementation.

### 920 2.4.1 Data Tokenization Appliance—StrongKey—Overview


921 The data tokenization appliance from StrongKey performs tokenization and secure storage in the PMS  
922 ecosystem.

923 The NCCoE used a remote instance of StrongKey Tellaro that may differ slightly from the physical device  
924 typically provided by StrongKey. The functionality provided to an adopting enterprise that implements a  
925 physical device will be the same, but the differences in requirements to support a physical device should  
926 be kept in mind.

927 We employed StrongKey Tellaro here to secure the point-of-sale transactions that occur in and around  
928 the property management system. In place of storing personal account numbers and other credit card  
929 information, StrongKey Tellaro creates a 16-digit token that is stored in place of the sensitive data.

930 The data tokenization appliance is employed primarily in the PMS, as shown in the figure below.

931 Figure 2-3 Data Tokenization Appliance in the Reference Architecture



932

### 933 2.4.2 Data Tokenization Appliance—StrongKey—Requirements

934 The following subsections document the software, hardware, and network requirements for the data  
935 tokenization appliance for StrongAuth KeyAppliance (SAKA) 4.0.

### 936 [2.4.2.1 Hardware Requirements for the Data Tokenization Appliance](#)

937 This installation imposes no hardware requirements.

### 938 [2.4.2.2 Software Requirements for the Data Tokenization Appliance](#)

939 Java Development Kit 8 Update 112 is required on any end point that will use the demo appliance.

### 940 [2.4.2.3 Network Requirements for the Data Tokenization Appliance](#)

941 The end point using the demo appliance must be able to connect to the appliance in question. For a  
942 remote installation, such as the one used by the NCCoE, the end point must be able to connect to the  
943 internet. For local installation, allow connection to the Tellaro device.

## 944 [2.4.3 Data Tokenization Appliance—StrongKey—Installation](#)

945 The majority of the instruction used in installation of the SAKA 4.0 demo is in the StrongKey SAKA Demo  
946 Client Guide Version 4.0 (<https://www.strongauth.com/pdf/SAKA-4.0-DemoClients.pdf>). Pay particular  
947 attention to Sections 3.1, 3.2, 3.3.1—Encryption and 3.3.2—Decryption. The remainder of the instructions  
948 below demonstrate how to integrate StrongKey into the PMS.

## 949 [2.4.4 Payment System Modifications](#)

950 To configure Solidres to tokenize credit card information (card owner’s name, card number, and card  
951 verification value [CVV]), we used StrongKey’s strong auth tokenization suite and modified the offline  
952 card of Solidres. In our ecosystem we modeled the offline plug-in, but similar feats can be accomplished  
953 by utilizing other plug-ins. The instructions below serve to tokenize credit card data from the front end.

- 954 1. Navigate to the directory containing the offline plug-in file in the solidrespayment folder. For our  
955 lab, this can be found here: `/var/www/html/joomla/plugins/solidrespayment/offline`
- 956 2. Move StrongKey’s `sakaclient.jar` file into this directory (ensure that you change the owner per-  
957 missions to `www-data` or `www`).
- 958 3. Open and edit the `offline.php`. Within the file, add the following lines in the `onReserva-`  
959 `tionAfterSave` function:

```
960     $data['offline']['cardnumber'] = substr(shell_exec("java -jar sakacli-  
961 ent.jar 'https://demo4.strongkey.com' 5 encryptonly [PASSPHRASE] EE' .  
962 data['offline']['cardnumber'] . " 1"), -16);
```

963

```
964     $data['offline']['cardcvv'] = substr(shell_exec("java -jar sakaclient.jar  
965 'https://demo4.strongkey.com' 5 encryptonly [PASSPHRASE] EE' . data['of-  
966 fline']['cardcvv'] . " 1"), -16);
```

967

```
968     $data['offline']['cardholder'] = substr(shell_exec("java -jar sakaclient.jar
969     'https://demo4.strongkey.com' 5 encryptonly [PASSPHRASE] ES' . data['of-
970     fline']['cardholder'] . " 1"), -16);
```

## 971 **2.5 Physical Access Control System—Häfele Dialock**

972 This section of the guide provides installation and configuration guidance for the physical access control  
973 system, which provides the back-end capability for the physical security functions within a hotel. This  
974 usually includes running electronic locks on hotel room doors but can also extend to elevator access and  
975 access to physical amenities.

976 Häfele Dialock is the physical access control system used in the example implementation.

### 977 **2.5.1 Physical Access Control System—Häfele Dialock—Overview**


978 The physical access control system from Häfele provides the physical access systems and the means to  
979 administer them in the PMS ecosystem.

980 Häfele Dialock provides physical security to a hotel room, as well as encoding and issuing room keys to  
981 open specific doors. The Häfele Dialock includes a back-end server to administer the functions of the  
982 physical components of the solution.

983 The location of the physical access control system in the reference architecture is highlighted in the  
984 figure below.

985 Figure 2-4 shows a high level architecture diagram that highlights the location of the Network Protection  
986 Device and the Protected Network Zone in the reference architecture.

987 Figure 2-4 Physical Access Control Server in the Reference Architecture



988 **2.5.2 Physical Access Control System—Häfele Dialock—Requirements**

989 The following subsections document the software, hardware, and network requirements for the physical  
990 access control system for Häfele Dialock 2.0.

991 *2.5.2.1 Hardware Requirements for the Physical Access Control System*

992 Successful operation of the physical access control system requires one or more Häfele Dialock 2.0 room  
993 locks, an encoding station (ES), and a mobile data unit (MDU).

994 Additionally, a back-end server must be used to administer all the physical components. This installation  
995 occurred on a machine with 1 CPU, 4 GB of memory, and 40 GB of storage.

996 *2.5.2.2 Software Requirements for the Physical Access Control System*

997 This build utilized a Windows Server 2012 OS for the back-end server. The installation must occur on a  
998 Windows Server capable of supporting or connecting to a Windows Microsoft SQL 2012 database.

999 *2.5.2.3 Network Requirements for the Physical Access Control System*

1000 In case a remote database is used in lieu of installing one on the back-end server, the network  
1001 connection must be accessible from the server to the database. Additionally, the back-end server must  
1002 be able to connect to the encoding station and to the PMS. In case the database is not already installed,  
1003 internet access is required during installation. Web access will also be required to the encoding station  
1004 from another device during configuration.

1005 Note that a zero trust networking solution such as CryptoniteNXT can limit availability of network  
1006 resources when improperly configured. For this reason, we recommend setting up and verifying Häfele  
1007 Dialock before applying the associated rules on the CryptoniteNXT device, as seen in [Section 2.1.8](#).

1008 **2.5.3 Physical Access Control System—Häfele Dialock—Installation**


1009 The installation procedure consists of the following steps:

- 1010 1. Run the installation media on the back-end server.
- 1011 2. Log in to the web portal to change the password and apply a license.
- 1012 3. Add the encoding station to the back-end server.
- 1013 4. Add the MDU to the back-end server.
- 1014 5. Set up a guest room and a physical access control area.
- 1015 6. Provision access to terminals.
- 1016 7. Program a physical terminal with the MDU.
- 1017 8. Create roles, groups, and users.


1018 The instructions below require that installation media for the back-end server, provided by Häfele, is  
1019 available on the installation target. If it is not already present, add it via external media or by a remote  
1020 file transfer.

## 1021 2.5.4 Server Installation

- 1022 1. Run the installation media.
- 1023 2. Read and accept the license agreement by selecting “**I accept the agreement**”:



- 1024
- 1025 3. Click **Next**.
- 1026 4. Uncheck “Perform Express-Setup”:




1027

1028

1029

5. Click **Next**.
6. Change the installation directory if desired:



1030


1031

7. Click **Next**.

1032

8. If you wish to utilize an existing database, select **"Use existing database."** Otherwise, leave Install Microsoft SQL Server selected:

1033




1034

1035

1036

9. Click **Next**.

10. Change the installation directory for Microsoft SQL Server if desired:



1037

1038


11. Click **Next**.

1039

12. Change the administrator password for "sa" user as well as the Dialock 2.0 database password.

1040

Change the database user and name of Dialock 2.0 database fields if desired:




1041

1042

13. Click **Next**.

1043

14. Change the communication server service information if desired:




1044

1045

1046

15. Click **Next**.


16. Change the schedule service information if desired.



1047

1048 17. Click **Next**.

1049 18. Change the message queue service information if desired:




1050

1051

1052 19. Click **Next**.


1053 20. Change the web service name if desired. Select **“Encrypted communication (SSL)”**:



1054


1055

21. Click **Next:**




1056

- 1057 22. Click Install.
- 1058 23. Wait for the installation to complete.
- 1059 24. Verify that “Start Dialock 2.0 now” is checked:




- 1060
- 1061 25. Click Finish.
- 1062 26. A web page should open automatically. If not, navigate to <https://localhost/dialock2/>:



1063


1064

27. Log in with the default credentials provided in the installation guide:




1065 28. Click the box next to the “Upload license file” to open a file explorer.

1066 29. Locate the license file for dialock2 and click **Open**:




1067


1068 30. Input the provided license key:



1069 31. Click Import:




1070 32. Click **admin** in the top right corner of the page:



1071

1072 33. Click "Change password."


1073 34. Enter the current password as well as a new password. Confirm the new password:



1074

1075

35. Click **OK**:



1076 36. Click **OK**.


## 1077 2.5.5 Dialock 2.0 Encoding Station Configuration

1078 1. Turn on the encoding station.

1079 2. Note the IP address displayed on the device.


1080 3. Connect the encoding station to a network where the displayed IP address is accessible.

1081 4. Open a web browser and navigate to the IP address.



1082


5. Sign in with the credentials provided in the installation guide:




1083

1084

6. Select **Network**:



1085 7. Check **DHCP**:



1086

1087 8. Click **Apply Changes**.


1088 9. The new IP address should be visible on the encoding station device.

## 1089 2.5.6 Dialock 2.0 Web Setup

### 1090 2.5.6.1 Adding the Encoder

1091 1. First, add the encoder if it has not already been detected. To do this, navigate to **Devices** >  
1092 **Coding Devices** by using the main menu.

1093 2. From there, you will see a menu titled "**Encoders list**", If you see your networked device as  
1094 shown below you can proceed to the next step. If not, continue following the instructions.



1095

1096 To add an encoder, proceed as follows:

1097 1. In the left-hand menu field, click **Create**.

1098 2. A selection window appears. Click the **Häfele Offline** field:



1099

1100 3. Complete the master data form:


1101 ○ The grayed-out fields contain unconfigurable preset terms.

1102 ○ Enter a name for the encoder.

1103 ○ Check the **“Secure connection”** box.

1104 ○ For DNS name/IP address, enter the IP address of the encoder found in the bottom area  
1105 of the display of the encoder.

1106 ○ In the Port field, enter the number for the corresponding port. In most cases, this  
1107 number is 8443:



1108

1109 4. Save your entries by clicking the **Save** icon in the left-hand menu.

1110 ○ Now check if the encoder has been set up successfully. Click the **Read transponder** icon  
1111 in the left-hand menu.

1112 ○ The encoder emits a beep. Next, place a transponder on the encoder. If the encoder has  
1113 been set up successfully, a window will open that lists the information of the  
1114 transponder.

### 1115 *2.5.6.2 Adding the MDU*

1116 **NOTE:** If a Java dialogue window opens during the following process, close the window. This may hap-  
1117 pen more than once. Click **Close** or **Run** to close the Java dialogue boxes, which could take several  
1118 minutes.

1119 1. Before installing and registering a new MDU, the MDU must be connected to the computer via  
1120 the Universal Serial Bus port. If an AutoPlay window opens after connecting MDU, click the **X** to  
1121 close the window.

### 1122 *2.5.6.3 Setting Up a Guest Room*

1123 1. Navigate to **Devices > Terminal**. You should see the following window after successfully  
1124 navigating to this area.

1125 2. In this menu, select the “**create menu item**” located under Actions on the left side of the screen.  
1126 In the preselection pop-up dialogue, select **Häfele Offline (DG2)**.

1127 3. The grayed-out fields contain unconfigurable preset terms.

1128 4. Name is a required field. We recommend entering the room number as the name—for example,  
1129 102. The field for the installation location is optional.

1130 5. The **Save** icon in the left-hand menu field will flash.

1131 6. Save the entries:

1132

1133 Next, assign an area to the terminal.


- 1134 1. Click the **clipboard** icon to the right of the term Area to open a window in which different areas  
1135 are listed. Click the desired area. In the example below, Hospitality Lab was chosen. The window  
1136 closes and your selection is automatically copied to the current window. If you cannot select an  
1137 area, you will need to create one.

1138

- 1139 2. Click **Save** to save your entries.

1140 **2.5.6.4 Create an Area**

- 1141 1. Navigate to **Organization > Area** to create an area. In the menu, select the **Create** button in the  
1142 Actions menu on the left. In the preselection pop-up dialogue, select **DG2**. In this menu, give the  
1143 area a name and add the correct corresponding time zone before saving. In our lab, our  
1144 configuration looks like the following screen:



- 1145  
1146 2. Be sure to save the created area. After this is complete, refer to the previous step to add the  
1147 area to the terminal.

1148 **2.5.6.5 Provisioning Access**

1149 When configuring and commissioning a hotel, individual access rights must be assigned to the offline  
1150 terminals. The steps below describe the assignment of individual access rights.


1151 **2.5.6.5.1 Create Authorizations**

- 1152 1. To begin provisioning access to a created area and terminal, navigate to **Authorizations >**  
1153 **Individual Access Rights** in the top menu:



- 1154  
1155 2. When the window opens, select **“create.”**  
1156 3. The window **“Create Diallock 2.0 individual access rights”** opens.

- 1157 4. Enter the room number in the entry field for **Name** (the software accepts numbers only, not  
1158 letters), and click **Save**.
- 1159 5. The window “Create individual access rights” will open again. Your room number has already  
1160 been automatically copied to the uppermost input field.
- 1161 6. In the right input field for ID, enter the same room number already entered in the **Name** field.  
1162 (The fields must match.)
- 1163 7. Save the entries:



The screenshot shows a software window titled "Edit Dialock 2.0 individual access rights". The window has a red header bar with the title and navigation icons. Below the header, there are four input fields: "Name \*" containing "102", "Platform \*" containing "DG2", "ID" containing "102", and "Cross-area" with a dropdown arrow.

1164  
1165

#### 1166 [2.5.6.5.2 Configuring the Terminal](#)

1167 This step completes the individual terminal setup and assigns the previously created individual access  
1168 rights to the respective terminals.

- 1169 1. Navigate to **Devices > Terminal** in the main menu. In this menu, select the terminal that you  
1170 previously created. The **Edit Offline terminal** window opens.
- 1171 2. Click the “Individual access rights” tab.
- 1172 3. Click the **clipboard** below the term “Access rights.”
- 1173 4. This opens a dialogue box in which a selection of terminals that have already been set up are  
1174 listed:



1175

1176 5. Click the terminal that you created previously.

1177 6. Confirm with "Apply selection."

1178 7. The **Save** icon starts flashing. Click **Save**.

1179 8. You have now set up a terminal with its individual properties and assigned this terminal to a specific access point in the building.

1181 **2.5.6.5.3 Configuring the MDU**

1182 1. Navigate to **Devices > MDU**. A window with the heading **DG2-MDUliste** opens. If you have an MDU registered, you can skip to the next section.

1184 2. Select **Register MDU** on the left side of the screen. After accepting the Java applets run warnings, wait for the MDU to be discovered.

1186 3. If the MDU is plugged into the current host machine and you can view it in a file browser, you will see a window showing the discovered MDU. Close the window.

1188 4. Your MDU is now listed in the **DG2-MDUliste** menu:



- 1189 **2.5.6.5.4 Programming a Physical Terminal by Using the MDU**
- 1190 1. To program the physical terminal, navigate to **Organizations > Area**.
- 1191 2. Select the area that was created in the step Create an Area.
- 1192 3. Select **Parameterize MDU** from the left-hand menu.
- 1193 4. Ensure that your MDU is still plugged into your workstation. In the pop-up menu, select the
- 1194 rooms that you wish to program, then click **OK**.
- 1195 5. Depending on how many rooms you are programming, you will see a progress bar that then
- 1196 leads to a blank window stating the MDU has been programmed.
- 1197 6. Click **OK**. You can now begin to program physically access points utilizing the MDU.


### 1198 **2.5.6.6 Group and Role Creation**

1199 Multiple user roles can be created with different levels of access to the software. These roles can be

1200 assigned to different users created in the system.

#### 1201 **2.5.6.6.1 Creating a Role**

- 1202 1. Navigate to **System > Users** roles in the main menu. This opens the “User roles list” window.
- 1203 2. Select **Create** in the left-hand menu. The **Create user role** window opens.
- 1204 3. In the “**Role name**” field, enter an appropriate designation, such as “hotel manager” or “jani-
- 1205 tor.” Assign the desired authorizations to this user role. (Note the red triangles, which allow you
- 1206 to expand further windows to assign more detailed authorizations.) Save your entries:



1207

1208

1209 [2.5.6.6.2 Creating a User](#)

1210

1. Navigate to **System > Users** in the main menu.

1211

2. The “Users list” window opens. In the left-hand menu field, select **Create**.

1212

3. The “Create user” window opens. If a user will have full unrestricted access to the software, select **Administrator**. Otherwise, do not check this box, then continue. Complete the username, full name, and password. NOTE: The username and password are required to access the software.


1213

1214

1215

1216

4. Click **Save**:




1217

- 1218 5. Click the **Authorizations** tab at the top. From the existing users' roles, select the role that you  
 1219 wish to assign the user.

## 1220 2.6 Privileged Access Management System—Remediant SecureONE

1221 This section of the guide supplies installation and configuration guidance for the privileged access  
 1222 management solution, which provides security for administrator-level actions within the enterprise.

1223 Remediant SecureONE is the privileged access management solution within the reference architecture.



1224 **2.6.1 Privileged Access Management System—Remediant SecureONE—Overview**


1225 Remediant SecureONE provides detection and response capabilities for violations of privileged access  
1226 within the enterprise.

1227 In the PMS ecosystem, SecureONE was deployed as a prebuilt VM appliance from the vendor. We  
1228 configured the appliance with parameters necessary for our environment.

1229 The network security in place in the architecture relies on the appropriate authentication of privileged  
1230 users. Once that authentication is secured, it is trusted. It is the purview of the PAM solution to prevent  
1231 abuse of this trust.

1232 The location of the PAM system in the reference architecture is highlighted in the figure below.

1233 Figure 2-5 Privileged Access Management System in the Reference Architecture



1234

## 1235 2.6.2 Privileged Access Management System—Remediant SecureONE— 1236 Requirements

1237 The following subsections document the software, hardware, and network requirements for the PAM  
1238 system Remediant SecureONE. Both the hardware and software requirements were included in the  
1239 managed deployment provided by Remediant.

### 1240 *2.6.2.1 Hardware Requirements for the Privileged Access Management System*

1241 This installation occurred on a machine with 4 CPUs, 8 Gigabytes (GB) of memory, and 100 GB of  
1242 storage.

### 1243 *2.6.2.2 Software Requirements for the Privileged Access Management System*

1244 This build utilized an Ubuntu 14.04 OS for the SecureONE server.

### 1245 *2.6.2.3 Network Requirements for the Privileged Access Management System*

1246 Network connectivity must be available to the web server hosted on the Remediant SecureONE device.

1247 Please note that a zero trust networking solution such as CryptoniteNXT can limit availability of network  
1248 resources when improperly configured. For this reason, we recommend setting up and verifying  
1249 Remediant SecureONE before applying the associated rules on the CryptoniteNXT device, as seen in  
1250 [Section 2.1.8](#).

## 1251 *2.6.3 Privileged Access Management System—Remediant SecureONE—Installation*

1252 The installation procedure consists of the following steps:

- 1253 1. Connect SecureONE to the domain.
- 1254 2. Synchronize SecureONE to the domain.
- 1255 3. Verify that all managed machines are present in the SecureONE appliance.

1256 In the example implementation, SecureONE was deployed as a prebuilt VM from the vendor. The  
1257 instructions below assume that the VM is already deployed and is accessible from the network.

1258 For a more in-depth discussion of implementation of a PAM solution, particularly as it relates to an  
1259 installed access control platform, please see NIST Special Publication 1800-18, *Privileged Account*  
1260 *Management for the Financial Services Sector* Practice Guide.


### 1261 *2.6.4 Initial Configuration*

1262 SecureONE needs to be configured to connect to a domain server, which should be installed within your  
1263 environment. To have a successfully working SecureONE instance, take these steps:

- 1264 1. Create a service account within your Active Directory server. The service account can be named  
1265 secureone or anything that you choose. The SecureONE appliance will use this account.  
1266 [https://blogs.technet.microsoft.com/askpfplat/2012/12/16/windows-server-2012-group-man-](https://blogs.technet.microsoft.com/askpfplat/2012/12/16/windows-server-2012-group-managed-service-accounts/)  
1267 [aged-service-accounts/](https://blogs.technet.microsoft.com/askpfplat/2012/12/16/windows-server-2012-group-managed-service-accounts/)

1268 2. To log in to the SecureONE appliance, navigate in a web browser to the IP of the machine, and  
1269 use the provided credentials to sign in.

1270 3. On the side panel, select **Configure > Services:**



1271

1272 4. Select **Add Domain** in the Domain Configuration window.

1273 5. Enter your relevant domain information. We have included ours below for reference:

New Domain

---

#### Directory Connection Settings

Domain Name	<input type="text" value="hotel.nccoe"/>	<input type="button" value="Detect"/>
LDAP Server	<input type="text" value="win-hotel.hotel.nccoe"/>	
LDAP Port	<input type="text" value="389"/>	<input type="checkbox"/> SSL
Search Base	<input type="text" value="dc=hotel,dc=nccoe"/>	
Bind DN	<input type="text" value="HOTEL\secureone"/>	
Bind Password	<input type="password" value="*****"/>	
<input type="button" value="Test Connection"/>		
✔ Connection was Successful		

#### Scan Mode Settings

Domain User (Read-Only)	<input type="text" value="HOTEL\secureone"/>
Domain Password	<input type="password" value="*****"/>
Default Policy	<input type="text" value="Enabled"/>

#### Protect Mode Settings

Domain User	<input type="text" value="HOTEL\manager"/>
Domain Password	<input type="password" value="*****"/>
Default Policy	<input type="text" value="Disabled"/>


#### Directory Search Settings

Page Size	<input type="text" value="1000"/>	Search Scope	<input type="text" value="Subtree"/>
-----------	-----------------------------------	--------------	--------------------------------------

Activate Window  
Go to System in Contr  
Windows.

1274

1275 6. After the domain has been added, Remediant will sync with the domain. If the sync is successful,  
1276 you will see this screen:




1277

1278

1279

- If you return to the **Home** menu, your dashboard should start populating with the machines that are connected to the domain.



1280

## 1281 2.7 Wireless Network Management—Forescout CounterACT

1282 This section of the guide supplies installation and configuration guidance for the wireless network  
 1283 management solution, which provides access control for connections across the wireless network. It  
 1284 differentiates among verified guests, employees, and system administrators to provide the appropriate  
 1285 level of access through the wireless network.


1286 Forescout CounterACT is the wireless network management solution used in the example  
 1287 implementation.

1288 **2.7.1 Wireless Network Management–Forescout CounterACT–Overview**

1289 The wireless network management solution from Forescout administers the wireless network in the  
1290 PMS ecosystem.

1291 Forescout CounterACT authenticates users to the wireless network via a captive portal. It blocks  
1292 unauthenticated or unauthorized connections. Guests get access to the internet but not to internal  
1293 enterprise systems. Authenticated employees get access to the PMS so they can manage reservations  
1294 and perform other enterprise functions. The location of the wireless network management solution in  
1295 the reference architecture is highlighted in the figure below.

1296 Figure 2-6 Wireless Network Management in the Reference Architecture



1297

## 1298 2.7.2 Wireless Network Management–Forescout CounterACT–Requirements

1299 The following subsections document the software, hardware, and network requirements for the  
1300 wireless network management solution for version 8.1.

### 1301 2.7.2.1 Hardware Requirements for Wireless Network Management

1302 This installation occurred on a machine with 4 CPUs, 10 GB of memory, and 200 GB of storage.

1303 [2.7.2.2 Software Requirements for Wireless Network Management](#)


1304 This installation occurred on a deployed CentOS 7 VM that the vendor provided.

1305 [2.7.2.3 Network Requirements for Wireless Network Management](#)

1306 Forescout CounterACT requires the capability to monitor network traffic on the network it is  
1307 administering. Network connectivity is also required on the user workstation that will run the Forescout  
1308 CounterACT console.

1309 [2.7.3 Wireless Network Management—Forescout CounterACT—Installation](#)

- 1310 1. To install the CounterACT console for management, navigate to [FORESCOUT IP]/install. This  
1311 leads you to the page where you need to download the management console.



- 1312
- 1313 2. After installing the console, you can then log in to the management interface to begin configur-  
1314 ing your Forescout CounterACT appliance.



1315

1316

1317

3. Navigate through the Initial Setup Wizard when the console launches. Verify that the time and NTP server are configured as desired.

**Initial Setup Wizard**

Welcome  
 License  
 **Time**

**Time**

Use this option to set the CounterACT Appliance time zone. Set a time zone according to geographic location or by GMT offset.

Local time Wed May 29 10:46:25 2019  
 GMT time Wed May 29 14:46:25 2019  
 Time Zone

NTP Server

Mail  
 User Directory  
 Domains  
 Authentication Servers  
 Internal Network  
 Enforcement Mode  
 Channels  
 Switch  
 Policy  
 Inventory  
 Finish

1318

1319

4. Input the e-mail account that you wish to receive notifications and alerts to.

**Initial Setup Wizard**

Welcome  
 License  
 Time  
 **Mail**

**Mail**

Use this option to set Admin email information used for sending CounterACT notifications and alerts. If your network requires a mail relay, enter the mail relay address and verify that the mail relay server can receive mail from the CounterACT Appliance.

Admin Email   
 Mail relay

User Directory  
 Domains  
 Authentication Servers  
 Internal Network  
 Enforcement Mode  
 Channels  
 Switch  
 Policy  
 Inventory  
 Finish

1320

1321

5. Input the domain information and credentials to be employed by ForeScout CounterACT.

### Initial Setup Wizard

- Welcome
- License
- Time
- Mail
- User Directory**
- Domains
- Authentication Servers
- Internal Network
- Enforcement Mode
- Channels
- Switch
- Policy
- Inventory
- Finish

#### User Directory

Use this option to define credentials for a LDAP Server. These credentials are used to authenticate users and resolve user information, for example the display name, department name, e-mail address and more. You can later define other servers from Tools>Options>User Directory Plugin screen.

Name:

Type:

Communication

Address:   DNS Detection

Port:   Use TLS

Directory

Domain:

*[Example: Fully Qualified Domain Name, e.g. MyCompany.com]*

Administrator:

Password:

Verify Password:

1322

1323

6. Input the IP Address range to be provisioned to the wireless network.

### Initial Setup Wizard

- Welcome
- License
- Time
- Mail
- User Directory
- Domains
- Authentication Servers
- Internal Network**
- Enforcement Mode
- Channels
- Switch
- Policy
- Inventory
- Finish

#### Internal Network

The Internal Network is the range of IP addresses in your organization that you want CounterACT to manage. It is recommended that you include your entire organizational network in this definition, including unused IP ranges. IPs outside this range will not be handled by the Appliance. Hosts in the Internal Network must be visible to CounterACT Appliances.


Assign a segment name to the Internal Network for easy identification.

Segment name:


Ranges

Range
<div style="border: 1px solid #ccc; padding: 5px; margin-bottom: 5px;"> <p><b>IP Address Range</b></p> <p>IP Range or Subnet: <input type="text" value="192.168.0.0/24"/></p> <p>Examples:</p> <ul style="list-style-type: none"> <li>● 10.0.0.1 - 10.0.0.127</li> <li>● 192.168.1.0/24</li> <li>● 10.0.0.1</li> <li>● fd00::8</li> <li>● 2001:db8::1</li> </ul> <p style="text-align: right;"> <input type="button" value="OK"/> <input type="button" value="Cancel"/> </p> </div>

- 1324 7. Set the enforcement options desired for this deployment. For our lab, "Full Enforcement with  
 1325 NAT Detection and Auto Discovery were employed.



- 1326 8. Start the appliance in the options windows. You can open the options menu by selecting the  
 1327 gear on the right of the screen.  
 1328



1329 **2.7.4 DNS Enforcement**

- 1330 1. In the options menu, select the drop-down for modules, then select **DNS Enforce**. In this menu,  
1331 configure the IP used for the DNS enforcement. It should look like the screenshot below.



1332

1333 **2.7.5 Switch Plug-in**

- 1334 1. In the options menu, select the switch menu icon in the left scrolling menu. Here, we are adding  
1335 our VyOS switch:

- 1336
  - Select **Add**.
- 1337
  - Enter the address of the switch.
- 1338
  - Select **Router-Linux** as the vendor:



- 1339 2. Enter the authentication credentials of the switch to enable CLI management via the Forescout  
1340 CounterACT appliance.

**CLI**  
Configure the plugin to connect to the managed switch using CLI credentials - either Telnet or SSH credentials.

Use CLI

Connection Type SSH

User admin

Password \*\*\*\*\*

Confirm Password \*\*\*\*\*

**Privileged Access Parameters**

Enable privileged access

No password

Use login parameters


Custom

User

Password


Confirm Password

- 1341
- 1342 3. Verify that **Read: IP to MAC Mapping** is checked.



1343

1344 4. Configure 802.1X per organizational specification.



1345

1346 5. Start and test your switch configuration, selecting **start** and **test** respectively.

## Add Switch

- General
- CLI
- Permissions
- 802.1X

### CLI

Configure the plugin to connect to the managed switch using CLI credentials - either Telnet or SSH credentials.

Use CLI

Connection Type: SSH

User:

Password:

Confirm Password:

#### Privileged Access Parameters

Enable privileged access

No password

Use login parameters

Custom

User:

Password:

Confirm Password:

#### SSH Fingerprint

Use SSH Fingerprint

A  
G  
V

1347

1348 **2.7.6 Guest Policy**

1349 The guest policy is defined to control access of a hotel guest when that person is using Guest WiFi  
 1350 according to the authentication results of the hotel guest device. The authentication process determines  
 1351 the access to which the hotel guest device qualifies, then Forescout implements the controls to provide

1352 the correct access. It is assumed, due to limitations of the NCCoE lab, the actual authentication process  
1353 is completed.

1354 Our lab uses three devices connected to the Guest WiFi to represent the three results that may come  
1355 from the authentication process: Guest Hosts, Signed-in Guest Hosts, and Corporate Hosts. These names  
1356 relate to those used by the Forescout tool.

1357     • Guest Hosts

1358         ○ end-point client devices that are not authenticated

1359         ○ No traffic is allowed from these devices within the Wi-Fi VLAN.

1360         ○ In the Forescout console, this type of device is shown in the Policy Guest WiFi column as  
1361         Guest Hosts. This device is identified by the IP address 192.168.0.129.

1362     • Signed-in Guest Hosts

1363         ○ end-point client devices that are authenticated as hotel guests with approved access to  
1364         the internet

1365         ○ Allow traffic on ports 80 and 443 to addresses outside the hotel on the internet (non-  
1366         RFC1918 addresses).

1367         ○ Prevent access to any addresses inside the hotel infrastructure (RFC1918 addresses).

1368         ○ In the Forescout Console, this type of device is shown in the Policy Guest WiFi column as  
1369         Signed-in Guests. This device is identified by the IP address 192.168.0.119.

1370     • Corporate Hosts

1371         ○ end-point client devices that are authenticated with hotel domain credentials

1372         ○ Allow full access to both the internet (non-RFC1918 addresses) and addresses inside the  
1373         hotel infrastructure (RFC1918 addresses).

1374         ○ In the Forescout Console, this type of device is shown in the Policy Guest WiFi column as  
1375         Corporate Hosts. This device is identified by the IP address 192.168.0.133.


1376 This Forescout policy is designed to detect a device when it joins the Guest WiFi, query that device for  
1377 the result of its authentication process and assign settings to the Forescout virtual firewall that provide  
1378 the appropriate network access to that device. Due to lab limitations, the query process is not part of  
1379 this guide, and the devices in the lab are manually assigned to each of the three devices used in the lab.

1380 The Forescout policy is defined by these parameters:

1381     ▪ Name: Guest WiFi

- 1382      ▪ Scope: wireless network segment in the lab and any computer or mobile device
- 1383      ▪ Main Rule: This is not used for this lab.
- 1384      ▪ Sub-Rules: Three subrules identify and control the three types of hotel guest devices instead of
- 1385      the Main Rule.
  - 1386          • Name:
    - 1387              ▪ Corporate Hosts
    - 1388              ▪ Signed-in Guests
    - 1389              ▪ Guest Hosts
  - 1390          • Condition:
    - 1391              ▪ Match a single criterion.
      - 1392                  ▪ IPv4 address
        - 1393                      • 192.168.0.133
        - 1394                      • 192.168.0.129
        - 1395                      • 192.168.0.119
  - 1396          • Action:
    - 1397              ▪ Add to Group.
      - 1398                  • Designate Corporate Hosts.
      - 1399                  • Designate Signed-in Guests.
      - 1400                  • Designate Guest Hosts.
    - 1401              ▪ Virtual Firewall
      - 1402                  • blocking rules for Corporate Hosts
      - 1403                  • blocking rules for Signed-in Guests
      - 1404                  • blocking rules for Guest Hosts

1405      The Forescout console full screen showing the three devices on the Guest WiFi appears below.




1406


1407

1408

1. Right-click the **Guest WiFi** policy in the Views section of the Console and click **Edit** to open the policy editor and configure ForeScout for controlling the Guest WiFi.



- 1409 2. Start the configuration process by clicking **Edit** in the Name section and entering the name of  
1410 the policy.



- 1411  
1412 3. Click **Edit** in the Scope section to open the scope editor.

Policy: 'Guest WiFi' -

**Name**  
Name Guest WiFi

Policy: 'Guest WiFi'-->Scope -

Hosts inspected by the policy

Segment ^	Ranges
Wireless	192.168.0.0/24

Add  
Remove  
Segments

Filter by Group - Only inspect hosts from the following groups

Group ^	Description
Linux/Unix	Classifier group
Macintosh	Classifier group

Add  
Remove


Exceptions - Do not inspect the following

Type ^	Values
No items to display	


Add  
Edit  
Remove


Help OK Cancel

- 1413 4. Click **Add** in the “Hosts Inspected by the policy” section to open the IP Address Range window  
1414 and select the network segment to be monitored.



- 1415  
1416 5. Click **Add** in the “Filter by group” section to open the Groups window and select the types of de-  
1417 vices to be monitored.







1418

1419 After the Name and Scope have been defined, consider defining the Main Rule section. For this lab, the  
1420 Main Rule was left in the default No Conditions value. Only the Sub-Rules were used.

1421 1. Highlight a Sub-Rule and click **Edit** to open the Sub-Rule edit window.




- 1422      2. In the Sub-Rule edit window, click **Edit** in the Name section, and enter the name of the Sub-Rule.



- 1423
- 1424      3. In the Condition Section of the Sub-Rule edit window, click the drop-down arrow, and select the
- 1425      **condition type.**
- 1426      4. Then highlight the Criteria and click **Edit** to open the Condition Edit window:

1427




1428  
1429  
1430  
1431

- The left frame of the Condition Edit window lists the conditions that Forescout may use. Scroll through the list and select the appropriate Condition. This lab used the IPv4 Address Condition to identify the device used for each of the three types of hotel guest devices.


1432  
1433  
1434

We needed a work-around to address limitations in the lab. In a real-world situation, dynamic criteria tailored to meet the strategy of a specific hotel, such as the Authentication Login Condition, may be appropriate:



1435  
1436  
1437

- In the Actions Section of the Sub-Rule edit window, highlight the Action in the box, and click **Edit** to open the Action Edit window:




1438

1439

1440

1441

- The left frame of the Action Edit window lists the actions that Forescout may use. Scroll through the list and select the appropriate action. This lab used the Add to Group action to designate the device identified by the condition as one of the three types of hotel guest devices:



1442


1443

1444

1445

1446

- This lab also used the Virtual Firewall action to control the access given to the device identified by the condition as one of the three types of hotel guest devices. In the **Action Edit** window for the Virtual Firewall, select the blocking rule that matches the appropriate type of hotel guest device, and click **Edit** to open the **Blocking Rules Edit** window:




1447

1448

1449

9. In the **Blocking Rules Edit** window, select the Inbound/Outbound criteria, the Target IP range, and the Target Port range for the rule:



## 1450 2.8 Virtual Switch—VyOS Configuration

1451 We configured a VyOS router to work with Forescout’s switch plug-in to capture and enforce the  
 1452 policies we deployed for the wireless network. VyOS is a console-based Linux switch/firewall and  
 1453 was used as a virtual switch in our use case.

1454 To begin configuring the switch, we used the following commands. VyOS has good  
 1455 documentation, and we recommend that you reference the documentation if you would like to  
 1456 extend the capabilities of the machine.

```
1457     $ configure
1458     set interfaces eth2 address dhcp
1459     set interface eth2 description 'OUTERNET'
1460     set interface eth1 address '192.168.0.1/25'
1461     set interface eth1 description 'WIRELESS'
```

1462 set service ssh port '22'

1463 set nat source rule 100 outbound-interface 'eth1'

1464 set nat source rule 100 source address '192.168.0.0/24'

1465 set nat source rule 100 translation address masquerade

1466 set service dhcp-server shared-network-name LAN subnet 192.168.0.0/24 de-  
1467 fault-router '192.168.0.1'

1468 set service dhcp-server shared-network-name LAN subnet dns-server [FORESCOUT  
1469 DNS-ENFORCEMENT IP]

1470 set service dhcp-server shared-network-name LAN subnet dns-server  
1471 '192.168.0.1'

1472 set service dhcp-server shared-network-name LAN subnet domain-name 'hotel-  
1473 wireless'

1474 set service dhcp-server shared-network-name LAN subnet lease '86400'

1475 set service dhcp-server shared-network-name LAN subnet range 0 start  
1476 192.168.0.10

1477 set service dhcp-server shared-network-name LAN subnet range 0 stop  
1478 '192.168.0.254'

1479 set service dns forwarding cache-size '0'

1480 set service dns forwarding listen-on 'eth1'

1481 set service dns forwarding name-server '8.8.8.8'

1482 set service dns forwarding name-server '1.1.1.1'

1483 set traffic-policy shaper WAN-OUT bandwidth '50Mbit'

1484 set traffic-policy shaper WAN-OUT default bandwidth '50%'

1485 set traffic-policy shaper WAN-OUT default ceiling '100%'

1486 set traffic-policy shaper WAN-OUT default queue-type 'fair-queue'

1487 set traffic-policy shaper LAN-OUT bandwidth '200Mbit'

1488 set traffic-policy shaper LAN-OUT default bandwidth '50%'

1489 set traffic-policy shaper LAN-OUT default ceiling '100%'

1490 set traffic-policy shaper LAN-OUT default queue-type 'fair-queue'

1491 set interfaces ethernet eth1 traffic-policy out 'LAN-OUT'

1492 set interfaces ethernet eth2 traffic-policy out 'WAN-OUT'

1493 set service snmp community hospitality routers authorization ro

1494 set service snmp community hospitality routers client [FORESCOUT APPLIANCE]

```
1495     set service snmp trap-target [FORESCOUT APPLIANCE]
1496     set service snmp v3 engineid '0x0aa0d6c6f450'
1497     set service snmp v3 group defaultgroup mode 'ro'
1498     set service snmp v3 group defaultgroup seclevel 'priv'
1499     set service snmp v3 group defaultgroup view 'defaultview'
1500     set service snmp v3 view defaultview oid '1'
1501     set service snmp v3 user hotel_user auth plaintext-key [STRONG PASSWORD]
1502     set service snmp v3 user hotel_user auth type 'md5'
1503     set service snmp v3 user hotel_user engineid '0x0aa0d6c6f450'
1504     set service snmp v3 user hotel_user group 'defaultgroup'
1505     set service snmp v3 user hotel_user mode 'ro'
1506     set service snmp v3 user hotel_user privacy type aes
1507     set service snmp v3 user hotel_user privacy plaintext-key [STRONG PASSWORD]
1508     $ commit
1509     $ save
```

## 1510 2.9 Integration of Security Components

1511 In addition to installation and configuration of the individual components, the PMS ecosystem required  
1512 a few commands to enable end points with native GUIs to work.

### 1513 2.9.1 CryptoniteNXT Integration with CLI End Points

1514 Typically, addition of an end point to the CryptoniteNXT protected zone is done through a web browser.  
1515 In the case of end points without native GUIs, specifically TDi ConsoleWorks and Remediant SecureONE,  
1516 the following steps must be taken. These instructions rely on CLI access to the end point in question.

```
1517     $sudo yum install wget
1518     $y
1519     $wget --no-check-certificate --post-data 'username=Administra-
1520     tor&passcode=<TOTP Code>' https://portal.di.ipdr/login
```

## Appendix A List of Acronyms

<b>ACC</b>	Administration Control Center
<b>CentOS</b>	Community Enterprise Operating System
<b>CLI</b>	Command Line Interface
<b>CNSSI</b>	Committee on National Security Systems Instruction
<b>CPU</b>	Central Processing Unit
<b>CRADA</b>	Cooperative Research and Development Agreement
<b>DNS</b>	Domain Name System
<b>FIPS</b>	Federal Information Processing Standards
<b>FQDN</b>	Fully Qualified Domain Name
<b>GB</b>	Gigabyte
<b>GUI</b>	Graphical User Interface
<b>IP</b>	Internet Protocol
<b>IT</b>	Information Technology
<b>LAN</b>	Local Area Network
<b>MDU</b>	Mobile Data Unit
<b>NCCoE</b>	National Cybersecurity Center of Excellence
<b>NIST</b>	National Institute of Standards and Technology
<b>OS</b>	Operating System
<b>PCI</b>	Payment Card Industry
<b>PHP</b>	Hypertext Preprocessor
<b>PMS</b>	Property Management System
<b>RDP</b>	Remote Desktop Protocol
<b>SAKA</b>	StrongAuth KeyAppliance
<b>SSH</b>	Secure Shell
<b>SSL</b>	Secure Sockets Layer

<b>SP</b>	Special Publication
<b>TCP</b>	Transport Control Protocol
<b>UDP</b>	User Datagram Protocol
<b>VLAN</b>	Virtual Local Area Network
<b>VM</b>	Virtual Machine
<b>VNC</b>	Virtual Network Computing

1522

## Appendix B Glossary

<b>Access Control</b>	<p>The process of granting or denying specific requests: 1) for obtaining and using information and related information processing services; and 2) to enter specific physical facilities (e.g., Federal buildings, military establishments, and border crossing entrances).</p> <p>SOURCE: Committee on National Security Systems Instruction (CNSSI) 4009-2015</p>
<b>Architecture</b>	<p>the design of the network of the hotel environment and the components that are used to construct it</p>
<b>Authentication</b>	<p>The process of verifying the identity of a user, process, or device, often as a prerequisite to allowing access to resources in an information system.</p> <p>SOURCE: Federal Information Processing Standards (FIPS) 200</p>
<b>Authorization</b>	<p>The right or a permission that is granted to a system entity to access a system resource.</p> <p>SOURCE: National Institute of Standards and Technology (NIST) Special Publication (SP) 800-82 Rev. 2</p>
<b>Certificate Revocation List</b>	<p>A list maintained by a Certification Authority of the certificates which it has issued that are revoked prior to their stated expiration date.</p> <p>SOURCE: NIST SP 800-32</p>
<b>Configuration</b>	<p>The possible conditions, parameters, and specifications with which an information system or system component can be described or arranged.</p> <p>SOURCE: NIST SP 800-128</p>
<b>Console</b>	<p>a visually oriented input and output device used to interact with a computational resource</p>
<b>Firewall</b>	<p>A part of a computer system or network that is designed to block unauthorized access while permitting outward communication.</p> <p>SOURCE: NIST SP 800-152</p>

<b>Fully Qualified Domain Name</b>	<p>an unambiguous identifier that contains every domain level, including the top-level domain</p>
<b>Information Security</b>	<p>The protection of information and information systems from unauthorized access, use, disclosure, disruption, modification, or destruction in order to provide confidentiality, integrity, and availability.</p> <p>SOURCE: FIPS 200</p>
<b>Multifactor Authentication</b>	<p>Authentication using two or more factors to achieve authentication. Factors include: (i) something you know (e.g., password/personal identification number [PIN]); (ii) something you have (e.g., cryptographic identification device, token); or (iii) something you are (e.g., biometric).</p> <p>SOURCE: CNSSI 4009-2015</p>
<b>Privilege</b>	<p>A right granted to an individual, a program, or a process.</p> <p>SOURCE: CNSSI 4009-2015</p>
<b>Public Key Infrastructure</b>	<p>The architecture, organization, techniques, practices, and procedures that collectively support the implementation and operation of a certificate-based public key cryptographic system. Framework established to issue, maintain, and revoke public key certificates.</p> <p>SOURCE: CNSSI 4009-2015</p>
<b>Security Control</b>	<p>A safeguard or countermeasure prescribed for an information system or an organization designed to protect the confidentiality, integrity, and availability of its information and to meet a set of defined security requirements.</p> <p>SOURCE: NIST SP 800-161</p>
<b>Wi-Fi</b>	<p>A generic term that refers to a wireless local area network that observes the IEEE 802.11 protocol.</p> <p>SOURCE: NIST Interagency or Internal Report 725</p>